AudioCodes One Voice ™ Operations Center

# AudioCodes Routing Manager (ARM) REST Application Programming Interface (API)

Version 9.4



# **Table of Contents**

1	RES	ST API	Overview	11
2	ARI	// Serv	er REST API	13
3	Тор	ology	Rest API	15
	·	3.1.1	Create Group	
		3.1.2	Update Group	
		3.1.3	Get API	
		3.1.4	Filter	
	3.2	Create	e Topology API	23
		3.2.1	Create Connection	
		3.2.2	Create Node Archive	
		3.2.3	Create Virtual Peer Connection	
		3.2.4	Create NOIR Rear	
		3.2.5 3.2.6	Create VOIP Peer	
		3.2.7	Create Group	
		3.2.8	Create Customer	
	3.3	Topol	ogy Update API	
	0.0	3.3.1	Update Connection	
		3.3.2	Update VoIP Peer	
		3.3.3	Update VoIP Peers Map Locations	
		3.3.4	Update Peer Connection	34
		3.3.5	Update Node	
		3.3.6	Update Nodes Map Locations	
		3.3.7	Update Routing Interface	
		3.3.8 3.3.9	Update Clusters	
		3.3.10		
	3.4		ogy Delete API	
		•	· · · · · · · · · · · · · · · · · · ·	
	3.5	•	logy Actions API	
		3.5.1 3.5.2	Sync all Nodes Action.	
		3.5.2	Sync Node ActionLock Node Action	
		3.5.4	Lock Peer Connection Action	
		3.5.5	Lock Router Action	
		3.5.6	Lock Customer Action	
		3.5.7	Lock Multiple Customers Action	
		3.5.8	Detach Peer Connection Action	
		3.5.9	Configure Node	49
4	Rou	iting A	\PI	51
	4.1	Get A	PI	51
		4.1.1	Get Filter	55
	4.2	Routir	ng Create API	56
		4.2.1	Routing Group Create API	56
		4.2.2	Routing Rule Create API	
		4.2.3	SIP Response Action Create	
	4.3	Routir	ng Update API	63
		4.3.1	Routing Rule Update API	
		4.3.2	Routing Group Update API	68
		4.3.3	SIP Response Action Update API	
	4.4	Routir	ng Delete API	70



	4.5	Test Route API	71
	4.6	Time-based Routing (TBR) API	78
		4.6.1 TBR Conditions Create API	78
		4.6.2 TBR Condition Update API	
		4.6.3 TBR Condition Delete API	
	4.7	Attribute Group API	
		4.7.1 Attribute Group Get API	
		4.7.2 Attribute Group Create API	
		4.7.3 Attribute Group Update API	
		4.7.4 Attribute Group Add\Remove Attributes API	
		4.7.6 Attribute Group Multiple Delete API	
5	Sec	urity Rest API	
	5.1	Get API	
	5.1		
	<b>-</b> 0		
	5.2	Security Create API	
		5.2.1 Create Operator	
	5.3	Security Update API	
		5.3.1 Update Operator	
	5.4	Security Delete API	91
		5.4.1 Delete Operator API	91
	5.5	Login API	92
	5.6	Azure AD for REST Requests Authentication	93
		5.6.1 Revoking Azure User Tokens	
6	Ser	ver Rest API	95
	6.1	Get API	95
	6.2	Servers Create API	
	0.2	6.2.1 Create Server	
	6.0		
	6.3	Server Update API	
	0.4	6.3.1 Update Server	
	6.4	Server Delete API	
		6.4.1 Delete Server API	
	6.5	Servers Group API	
		6.5.1 Get All Server Groups	
		6.5.2 Get Specific Server Group	
		6.5.3 Create Server Group API	
		6.5.5 Delete Server Group API	
7	Acti	ion Status API	
8		work Planner API	
	8.1	Get API	
	5.1	8.1.1 Filter	
	8.2	Network Planner Create API	
	0.2	8.2.1 Create Connection	
		8.2.2 Create PeerConnection	
		8.2.3 Add Node to ARM	
		8.2.4 Add VoIP Peer to ARM	
	8.3	Network Planner Update API	
		8.3.1 Update Connection	
		·	

		8.3.2	Update VOIP Peer	
		8.3.3	Update VoIP Peers Map Locations	
		8.3.4	Update Peer Connection	
		8.3.5 8.3.6	Update Node	
	8.4		rk Planner Delete API	
	8.5		rk Planner Actions API	
	0.5			
		8.5.1 8.5.2	Import Full Topology	
		8.5.3	Export Node	
		8.5.4	Lock Node Action	
		8.5.5	Lock Peer Connection Action	128
9	lden	tity		129
	9.1	_	기	
			Get Filter API	
	9.2		y Create API	
	0	9.2.1	Server Create API	
		9.2.2	Server Test API	
		9.2.3	User Group Create API	
		9.2.4	UserGroup Dry Run API	
		9.2.5	User Create API	
		9.2.6 9.2.7	Dictionary Attribute Create API	
	0.2		File Repository Create API	
	9.3		y Update API	
		9.3.1 9.3.2	Server Update API	
		9.3.2	User Update API	
		9.3.4	Dictionary Attribute Update API	
		9.3.5	File Repository Update API	
	9.4	Identity	y Delete API	152
		9.4.1	Server Delete API	
		9.4.2	User Group Delete API	
		9.4.3	User Delete API	
		9.4.4	Dictionary Attribute Delete API	
		9.4.5	File Repository Delete API	
10	Stati	stics F	REST API	156
	10.1		eport API	
		10.1.1	Top Routes Statistics	
			10.1.1.1 Filter	
11	Alar	ms His	story	163
	11.1	Get AF	ମ୍	163
			Get Filter API	
			Cursor API	
			Get Event Count API	
12	Activ	ve Alaı	rms	170
	12.1		ગ	
			Get Filter API	
			Cursor API	
	40.0		Get Alarm Count API	
	12.2	Update	e API	175



13	Alar	ms Additional Info	177
	13.1	Get Alarms Additional Info	177
	13.2	Test Alarms Additional Info	179
14	Sysl	og	181
		Get API	
		14.1.1 Get Filter	
	14.2	Create API	
		Update API	
		Delete API	
15	SNN	1P	186
		Get API	
		Create SNMP Target API	
		Update SNMP Target API	
		Delete SNMP Target API	
16		ernal Alarms	
10		Create External Alarm	
		Create Multiple External Alarms	
17		malization Group	
		Get API	
		Create Normalization Group API	
		Update Normalization Group Target API	
		Delete Normalization Group API	
	17.5	Test Normalization Group	
	47.0	17.5.1 Examples (Paletian of Paletian Phina)	
		Get Normalization Group Associations (Relationships)	
18	NTP	Server Rest API	203
		Get API	203
	18.2	Create NTP Server	204
		Update NTP Server	
	18.4	NTP Server Delete API	206
19	ARN	/ License	207
	19.1	Get License API	207
	19.2	Get ARM Machine ID	209
	19.3	Update License Key API	210
20	Con	figuration	212
	20.1	Normalization API	212
		20.1.1 Update Routing Normalization API	
		20.1.2 Get Routing Normalization API	
	20.2	License Configuration	214
		20.2.1 Get License Configuration	
	20.2	20.2.2 Update License Configuration	
	20.3	Routing Rule Configuration	
		20.0.1 Rodding Ruic Configuration	210

		20.3.2 Update Routing Rule Configuration	217
	20.4	Security Configuration	218
		20.4.1 Get Security Configuration	218
		20.4.2 Update Security Configuration	219
	20.5	Quality-based Routing Configuration	220
		20.5.1 Quality-based Routing Configuration	220
		20.5.2 Quality-based Routing Update Configuration	
	20.6	LDAP Authentication	
		20.6.1 Get LDAP Authentication Server	
		20.6.2 Update/Add LDAP Authentication Server	
		20.6.3 Test LDAP Authentication Server.	
	20.7	RADIUS Authentication	
		20.7.1 Get RADIUS Authentication Server.	
		20.7.2 Update/Add RADIUS Authentication Server	
	20.0	Azure Authentication	
	20.0	20.8.1 Get Azure Authentication Server	
		20.8.2 Update/Add Azure Authentication Server	
		20.8.3 Test Azure Authentication Server	
	20.9	Calls Configuration	
	20.0	20.9.1 Get Calls Configuration	
		20.9.2 Update Calls Configuration	
	20.10	ORegistered Users	
		20.10.1 Get Registered Users Configuration	
		20.10.2 Update Registered Users Configuration	
	20.11	1 Analytics	
		20.11.1 Get Analytics Configuration	
		20.11.2 Update Analytics Configuration	
		20.11.3 Restore Analytics to Default	
		20.11.4 Get Analytics Users	
	20.12	2Registration	238
		20.12.1 Get Registration	
		20.12.2 Update Registration	
	00.46	20.12.3 Get Registration Users	
	20.13	3Quota	
		20.13.1 Get Quota Configuration	
	00.4	20.13.2 Update Quota Configuration	
	20.14	4CAC	
		20.14.1 Get CAC Configuration	
21	Calls	S	246
	21.1	Get Calls Summary	246
		21.1.1 Filter	
	21 2	Get Specific Call	
		•	
22	Calls	s Quota	251
	22.1	Get Calls quota	251
		22.1.1 Filter	
	22.2	Add Calls Quota	
		Update Calls Quota	
		Delete Calls Quota	
	22.4	Delete Calls Quota	∠ეე



	22.5 Delete Multiple Calls Quota	255
23	WEB Services	257
	23.1 Get Web Services Templates	257
	23.2 Get Web Services Implementation	258
	23.3 Create Web Service Implementation	259
	23.4 Update Web Service Implementation	
	23.5 Delete Web Service Implementation	261
24	Certificates	263
	24.1 Get Certificate API	263
	24.2 Add Certificate API	264
	24.3 Delete Certificate API	
25	Policy Studio	266
	25.1 Get Policy Studio API	266
	25.2 Add Policy Studio API	
	25.3 Update Policy Studio API	
	25.4 Delete Policy Studio API	
26	CAC Profile	274
	26.1 Get CAC Profile	274
	26.1.1 Filter	
	26.2 Add CAC Profile	276
	26.3 Update CAC Profile	277
	26.4 Delete CAC Profile	278
<b>27</b>	Journal	279
	27.1 Get Journal	279
	27.1.1 Filter	280
	27.1.2 Get Specific Journal Entry	281
<b>28</b>	Logging	283
	28.1 Client Logging into the Server	283
29	REST Responses Codes	285

Developer's Guide Notices

#### **Notice**

Information contained in this document is believed to be accurate and reliable at the time of printing. However, due to ongoing product improvements and revisions, AudioCodes cannot guarantee accuracy of printed material after the Date Published nor can it accept responsibility for errors or omissions. Updates to this document can be downloaded from <a href="https://www.audiocodes.com/library/technical-documents">https://www.audiocodes.com/library/technical-documents</a>.

This document is subject to change without notice.

Date Published: May-24-2021

#### **WEEE EU Directive**

Pursuant to the WEEE EU Directive, electronic and electrical waste must not be disposed of with unsorted waste. Please contact your local recycling authority for disposal of this product.

# **Customer Support**

Customer technical support and services are provided by AudioCodes or by an authorized AudioCodes Service Partner. For more information on how to buy technical support for AudioCodes products and for contact information, please visit our website at <a href="https://www.audiocodes.com/services-support/maintenance-and-support">https://www.audiocodes.com/services-support/maintenance-and-support</a>.

## Stay in the Loop with AudioCodes











# **Abbreviations and Terminology**

Each abbreviation, unless widely used, is spelled out in full when first used.

#### **Related Documentation**

Document Name	
ARM User's Manual	

#### **Document Revision Record**

LTRT	Description
41960	Initial document release for Version 7.2.
41961	Update of template with new AudioCodes logo.
41962	Updates for ARM Versions 7.4, 7.6, 7.8, 8.0, 8.2, 8.4 and 8.6
41963	Updates for ARM Versions 8.8, 9.0 and 9.2
41964	Updates to the Identity API for retrieving user items.



LTRT	Description
41965	Updates for ARM Version 9.4

## **Documentation Feedback**

AudioCodes continually strives to produce high quality documentation. If you have any comments (suggestions or errors) regarding this document, please fill out the Documentation Feedback form on our Web site at <a href="https://online.audiocodes.com/documentation-feedback">https://online.audiocodes.com/documentation-feedback</a>.

Developer's Guide 1. REST API Overview

# 1 REST API Overview

Why Restful API: Distributed systems over the WEB are widely spread both by the enterprise and core applications, and are the fundamental method used in the emerging Cloud Services.

WEB API is the main interface being used by such WEB services for communication between the elements distributed over the WEB, because it complies with the infrastructure and constraints defined by the WEB.

What is REST: REST is an architectural style and recommendations for WEB API, and not a strict standard and therefore it allows a high level of flexibility in implementation.

A Restful API is designed in a way that will accommodate to WEB infrastructure and fit the Web constraints.

REST adopts a fixed set of operations on named resources, where the representation of each resource is the same for retrieving and setting information. In other words, you can retrieve (read) data in a formatted method and also send data back to the server in similar format in order to set (write) changes to the system.

Operations on resources are implemented with the standard primitives (request methods) of HTTP:

- GET get information about list of resources or existing resource
- POST create new resource
- PUT –update existing resource
- DELETE delete existing resource

**JSON Encoding:** REST doesn't define which data encoding and formatting is to be used. The most commonly used methods are XML and JSON (JavaScript Object Notation).

Security: basic authentication will be used for each Rest request.

**Version Control:** REST API should be versioned (v1, v2 ...) so client-server communication and API methods can be verified as the same version. Backward compatibility between versions should be kept.



This page is intentionally left blank.

# 2 ARM Server REST API

The following shows the prefix URL for all REST requests:

<ARM\_Configurator\_IP>/ARM/v1

Where <ARM\_Configurator\_IP> is the IP address of the ARM Configurator.



This page is intentionally left blank.

# 3 Topology Rest API

This chapter describes the REST API resources for the Topology server. The following APIs are described:

- Create Group
- Update Group
- Get API
- Create Topology API

# 3.1.1 Create Group

The  $\ARM_Configurator_IP>/ARM/v1/topology/group$  URL when used with the POST method, provides the ability for the ARM Manager to send a request to the ARM Configurator to create a new group.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/topology/group

#### **HTTP Method**

POST

#### **Supported Content-Type**

application/json

#### **Attributes**

Attribute	Туре	Description
name	String	Group name: unique
elements	[ Integer ]	-
type	TopologyGroupType	TopologyGroupType: NODE PEER_CONNECTION VOIP_PEER

- 200 OK
- Topology Update API



## 3.1.2 Update Group

The <arm\_Configurator\_IP>/ARM/v1/topology/group/{id} URL when used with the PUT method provides the ability for the ARM Manager to send a request to the ARM Configurator to update a specific Group interface.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/topology/group/{id}

#### **HTTP Method**

PUT

#### **Supported Content-Type**

application/json

#### **Attributes**

It MUST contain the following arguments:

Attribute	Туре	Description
name	String	Group name: unique
elements	[ Integer ]	-

#### 3.1.3 Get API

The <code><ARM\_Configurator\_IP>/ARM/v1/topology/<ARM\_attribute> URL when used with the GET method provides the ability for the ARM Manager to send a GET Topology request to the ARM Configurator.</code>

#### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/topology/<ARM\_attribute>
<ARM Configurator IP>/ARM/v1/topology/<ARM\_attribute>/{id}

#### Where:

- <ARM\_attribute> requests all of the ids of the specified attribute (listed in the table below).
- {id} requests a specific ID of a specific attribute (listed in the table below).

#### HTTP Method

GET

#### **Supported Content-Type**

application/json

#### Attributes

The ARM Configurator must respond to the GET request with JSON data that includes the request URI attribute. If the ID is not specified in the GET request, the URI JSON data MUST contain an array of all specified elements defined in the database for the attribute.

Туре	Description
ARRAY OF:	Id – Node ID in the database
id: integer, operState: { description:String status:integer } adminState: string  name: string, ipAddr: string, hostname: String serialNum: string, deviceType: string url: string transportType:String islpProfileAvailable: Boolean routingServerPolicy:String productType:String routingServers: [ { id:Integer, priority:Integer, status:String } ] routingInterfaces: [ { Id: Integer udpPort: Integer tcpPort: Integer tlsPort: Integer name: String controllpAddr: String operativeState: ENUM nodeld: Integer srdld: String applicationType: ENUM isOffline: Boolean	operState:  0 = login 4 = logout 5 = unroutable 6 = invalid_configuration  adminState: 0 = unlock 1 = lock  teamsRole: 0 = NOT_TEAMS 1 = PROXY 2 = REMOTE  name - Name configured by ARM operator  deviceType: 1 = MEDIANT_1000 2 = MEDIANT_3000 3 = M3K_8410 4 = MEDIANT_600 5 = MP500_MSBG 6 = MEDIANT_1000_MSBG 7 = MEDIANT_1000_PRO 9 = MEDIANT_1000_PRO 9 = MEDIANT_4000_ESBC 10 = SW_SBC:int 11 = MEDIANT_500_MSBG 12 = MEDIANT_500_ESBC 13 = MEDIANT_500_ESBC 13 = MEDIANT_500L_ESBC 14 = MEDIANT_500L_ESBC 15 = MEDIANT_500L_ESBC 16 = MEDIANT_500L_ESBC 16 = MEDIANT_500L_ESBC 16 = MEDIANT_500L_ESBC 16 = MEDIANTG_800B_MSBR 17 = MEDIANTG_800B_ESBC 18 = SW_SE_SBC 19 = SW_SE_H_SBC 20 = SW_VE_SBC 21 = SW_VE_BBC 21 = SW_VE_H_SBC 22 = SW_9000_SBC 23 = ADC device- default device type URI - element REST path
	ARRAY OF: [



Attribute	Туре	Description
	} ] operatorld: Integer credentialsId: Integer routingServerGroupId: Integer supportedFeatures: ENUM topologyGroups: [ Integer ] teamsRole: ENUM }	transportType: HTTP HTTPS  routingServerPolicy: ROUND_ROBIN STICKY_PRIMARY STICKY_LAST_AVAILABLE
		productType: SBC GW HYBRID UNDEFINED or THIRD_PARTY  OperatorId – the ID of the operator that will be used by the node to login into ARM  CredentialsId – the ID of the credentials that the ARM will use when authenticating to the node
peerCon	ARRAY OF:  [      Id: integer     nodeld: integer,     nodeName: string,     name: string,     voipPeerId: integer     operState: string     adminState: string     voipPeer: integer,     routingInterface: integer, url: string  }	operState:  0 = created 1 = available 2 = not_available 3 = predeleted 4 = temp_not_available 5 = not_synced  adminState: 0 = unlock 1 = lock 2 = locked Incoming 3 = locked outgoing  url - element REST path
voippeer	ARRAY OF: [	deviceType:  0 = NA  1 = PSTN  2 = SIP_Trunk  3 = PBX  4 = IP_PBX  5 = IP_Phones  url – element REST path

Developer's Guide 3. Topology Rest API

Attribute	Туре	Description
	}	
connection	ARRAY OF:  [      id: integer     weight: integer     name: string,     URI: string,     adminState: string     connections:      [         {             srcNodeld: integer             destRoutingInterface: integer             destRoutingInterface: integer             operState: string     quality: {             "MOS": {                 measurement: Integer                 isUsed:Boolean         }     }     result: String(enum)  }  quality: {         "MOS": {                 isUsed:Boolean         }     }  result: String(enum)  }  result: String(enum)  }  result: String(enum)	By default each connection is two-way. Each direction has the following statuses: Direction 1 –from Node1 to Node2 Direction2- from Node2 to Node1 weight [1-100] Default =50 operState:  0 = available 1 = not_available 2 = predeleted 3 = temp_not_available 4 = not_synced adminState: 0 = unlock 1 = lock url – element REST path measurment – the reading that was received from the node isUsed – indicated whether the QoS attribute is taken into consideration when calculating the quality result the result of the quality calculation - enum BAD, FAIR, GOOD or UNKNOWN This value is sent for both connection nodes and the connection itself. type:  REGULAR LOOP_BACK NODE_TO_THIRD_PARTY



Attribute	Туре	Description
	type:String(enum)	
routingInterface	ARRAY OF: [	operState:  0= available 1 = not_available 2 = predeleted 3 = temp_not_available 4 = not_synced  transportType: UDP TCP TCP TLS  url – element REST path
nodeArchive	ARRAY OF: [	
cluster	{   id: String   x: Integer   y: Integer   nodes : [ Strings ]   name: String }	
group	{     id: Integer     name: String     elements: [ Integer ]     type: TopologyGroupType }	TopologyGroupType: NODE PEER_CONNECTION VOIP_PEER

Developer's Guide 3. Topology Rest API

Attribute	Туре	Description
registeredUsers	{   user: String   host: String   pConlds: [ Integer ]   nodeld: Integer }	
customer	id: Integer name: String cacState: String(Enum) adminState: String(Enum) attributeGroups: [Integer] sipHeaderName: String(Enum) sipHeaderValue: String, cacProfileId: Integer tag: String }	cacState:  0 = UNBLOCK  1 = BLOCK  2 = BLOCK_INCOMING  3 = BLOCK_OUTGOING  adminState:  1 = LOCKED  2 = UNLOCKED  sipHeaderName:  0 = CONTACT_HOST  attributeGroups:  Array of Attribute Groups ID's
customer\ sessionCount	id: Integer incomingCount: Integer outgoingCount: Integer cacld: Integer cacName: String cacTotalLimit: Long cacIncomingLimit: Long cacOutgoingLimit: Long	

- 200 OK
- 409 Conflict
- 500 Internal error



# **3.1.4** Filter

You can use a filter for specific requests. The filter should be added to the suffix of the URL, for example:

#### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/topology/peerCon?filter=(nodeId=100)

#### **HTTP Method**

GET

#### **Supported Content-Type**

application/json

#### **Supported Filter**

Filter	Available for these Requests	Description
nodeld	peerCon routingInterface	Filter results only for the node ID specified.
name	node	Contains for partial search Equals for regular search
serial	node	Filter by serial number
ipAddrr	node	Filter nodes by ip address
limit	voippeer, customer	Limits the number of items
page	voippeer, customer	Request a specific page
searchString	customer	Filter by all customer properties
name	customer	Filter by customer name
operativeState	customer	Filter by operative state
adminState	customer	Filter by admin state
sipHeaderName	customer	Filter by sip header name
sipHeaderValue	customer	Filter by sip header value
cacProfileId	customer	Filter by CAC profile
attrGroupsIds	customer	Filter by attr Group ID
tag	customer	Filter by tag

- 200 OK
- 409 Conflict
- 500 Internal error

# 3.2 Create Topology API

This section describes the API for creating Topology.

## 3.2.1 Create Connection

The <code><ARM\_Configurator\_IP>/ARM/v1/topology/connection</code> URL when used with the POST method, provides the ability for the ARM Manager to send a Create Connection request to the ARM Configurator.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/topology/connection

#### **HTTP Method**

POST

#### **Supported Content-Type**

application/json

#### Attributes

Attribute	Туре	Description
name	String	Unique name of the connection.
weight	integer	The weight of the connection.
connections	Array of two entries, one for each direction:  [	
type	String	REGULAR or NODE_TO_THIRD_PARTY

- 201 Created
- 409 Conflict
- 500 Internal Error



## 3.2.2 Create Node Archive

The <code><ARM\_Configurator\_IP>/ARM/v1/topology/nodeArchive</code> URL when used with the POST method, provides the ability for the ARM Manager to send a Create Node Archive request to the ARM Configurator.

#### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/topology/nodeArchive

#### **HTTP Method**

POST

#### **Supported Content-Type**

application/json

#### Attributes

Attribute	Туре	Description
nodeArchive	Array of [	The node details.

- 201 Created
- 409 Conflict
- 500 Internal Error

## 3.2.3 Create Virtual Peer Connection

The <code><ARM\_Configurator\_IP>/ARM/v1/topology/peerCon URL</code> when used with the POST method, provides the ability for the ARM Manager to send a Create Virtual Peer Connection request to the ARM Configurator.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/topology/peerCon

#### **HTTP Method**

POST

#### **Supported Content-Type**

application/json

#### Attributes

It MUST contain the following arguments:

Attribute	Туре	Description
name	String	The name of the virtual peer connection.
nodeld	Integer	The ID of the Virtual Peer node
voipPeerId	Integer	The ID of the voipPeerId node (optional)
weight	integer	The weight of the virtual peer node.

- 201 Created
- 409 Conflict
- 500 Internal Error



# 3.2.4 Create Routing Interface

The <code><ARM\_Configurator\_IP>/ARM/v1/topology/routingInterface</code> URL when used with the POST method, provides the ability for the ARM Manager to send a Create Routing Interface request to the ARM Configurator.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/topology/routingInterface

#### **HTTP Method**

POST

#### **Supported Content-Type**

application/json

#### **Attributes**

It MUST contain the following arguments:

Attribute	Туре	Description
name	String	The name of the routing interface.
controllpAddr	String	The IP address of the routing interface (SIP interface In the SBC).
tcpPort	Integer	The TCP port number (0 for none)
udpPort	integer	The UDP port number (0 for none)
tlsPort	integer	The TLS port number (0 for none)

The combination of IP address and the 3 ports must be unique.

- 201 Created
- 409 Conflict
- 500 Internal Error

# 3.2.5 Create VOIP Peer

The  $\ARM_Configurator_IP>/ARM/v1/topology/voippeer$  URL when used with the POST method, provides the ability for the ARM Manager to send a Create VOIP Peer request to the ARM Configurator.

#### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/topology/voippeer

#### **HTTP Method**

POST

#### **Supported Content-Type**

application/json

#### Attributes

Request must contain the following data elements:

Attribute	Туре	Description
deviceType	string	0=NA 1= PSTN 2= SIP_trunk 3= PBX 4= IP_PBX 5= IP_PHONES
name	string	Name of the VOIP peer

- 201 Created
- 409 Conflict
- 500 Internal Error



# 3.2.6 Add Node to ARM

The  $\ARM_Configurator_IP>/ARM/v1/topology/node$  URL when used with the POST method, provides the ability for the ARM Manager to send a request to the ARM Configurator to add a node.

#### **REST Resource**

<ARM Configurator\_IP>/ARM/v1/topology/node

#### **HTTP Method**

POST

#### **Supported Content-Type**

application/json

#### Attributes

Attribute	Туре	Description
ipAddr	String	The IP address / hostname of the node
userName	String	Optional
operatorId	Integer	Credentials that the node uses to communicate with ARM
credentialsId	Integer	Credentials used to communicate with the device.
name	String	Unique node name
transportType	String	HTTP or HTTPS
type	String	If Third-party then a 3rd party node will be created.
routingInterfaces	Routing interface Json	Optional
х	Integer	The value of the x coordinate.
у	Integer	The value of the y coordinate.

- 201 Created
- 409 Conflict
- 500 Internal Error

# 3.2.7 Create Group

The <code><ARM\_Configurator\_IP>/ARM/v1/topology/group</code> URL when used with the POST method, provides the ability for the ARM Manager to send a request to the ARM Configurator to create a new group.

#### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/topology/group

#### **HTTP Method**

POST

## **Supported Content-Type**

application/json

#### Attributes

Attribute	Туре	Description
name	String	Group name: unique
elements	[ Integer ]	
type	TopologyGroupType	TopogyGroupType: NODE PEER_CONNECTION VOIP_PEER

#### **HTTP Response**

200 OK



## 3.2.8 Create Customer

The <arm\_Configurator\_IP>/ARM/v1/topology/customer URL when used with the POST method, provides the ability for the ARM Manager to send a request to the ARM Configurator to create a new customer.REST Resource

<ARM Configurator IP>/ARM/v1/topology/customer

#### HTTP Method

POST

#### **Supported Content-Type**

application/json

#### Attributes

Attribute	Туре	Description
name	String	Customer name: unique
cacState	ENUM	operativeState: 0 = UNBLOCK 1 = BLOCK 2 = BLOCK_INCOMING 3 = BLOCK_OUTGOING
adminState	ENUM	adminState: 1 = LOCKED 2 = UNLOCKED
attributeGroups	[ Integer ]	Array of Attribute Groups ID's
sipHeaderName	ENUM	Header identification name sipHeaderName: 0 - CONTACT_HOST
sipHeaderValue	String	Header identification value
cacProfileId	Integer	CAC Profile ID

#### **HTTP Response**

200 OK

# 3.3 Topology Update API

This section describes the Topology Update API.

# 3.3.1 Update Connection

The <code><ARM\_Configurator\_IP>/ARM/v1/topology/connection/{id}</code> URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to update a specific connection.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/topology/connection/{id}

Where {id} is the ID of the connection.

#### **HTTP Method**

PUT

#### **Supported Content-Type**

application/json

#### Attributes

Attribute	Туре	Description
name	string	Name of the connection
weight	integer	Connection weight. 1-100 Default = 50

- 200 OK
- 409 Conflict
- 500 Internal Error



# 3.3.2 Update VoIP Peer

The <code><ARM\_Configurator\_IP>/ARM/v1/topology/voippeer/{id}</code> URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to update a specific VoIP Peer.

#### **REST Resource**

PUT <ARM Configurator IP>/ARM/v1/topology/voippeer/{id}

Where {id} is the ID of the VoIP Peer.

#### **HTTP Method**

PUT

#### **Supported Content-Type**

application/json

#### **Attributes**

Attribute	Туре	Description
deviceType	string	0 = NA 1 = PSTN 2 = SIP trunk 3 = PBX 4 = IP_PBX 5 = IP_PHONES
name	string	Name of the VoIP Peer

- 200 OK
- 409 Conflict
- 500 Internal Error

# 3.3.3 Update VoIP Peers Map Locations

The <code><ARM\_Configurator\_IP>/ARM/v1/topology/voippeer/location</code> URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to save the location of the VoIP peers elements.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/topology/voippeer/location

#### **HTTP Method**

PUT

#### **Supported Content-Type**

application/json

#### Attributes

Attribute	Туре	Description
id	Integer	Ξ.
х	Integer	X coordinate value
у	Integer	Y coordinate value

- 200 OK
- 409 Conflict
- 500 Internal Error



# 3.3.4 Update Peer Connection

The <ARM\_Configurator\_IP>/ARM/v1/topology/peerCon/{id} URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to update a peer connection.

#### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/topology/peerCon/{id}

Where {id} is the ID of the peer connection.

#### **HTTP Method**

PUT

#### **Supported Content-Type**

application/json

#### **Attributes**

Attribute	Туре	Description
name	string	Name of the peer connection.
voipPeerId	Integer	ID of the peer connection.
quality: { "MOS": {  isUsed:Boolean },  "ASR": {		isUsed: indicated whether the QoS parameter will be taken into consideration when calculating the quality, if this is NULL for all the quality parameters the default global settings will be used, otherwise local will be used
isUsed:Boolean }		
}		

- 200 OK
- 409 Conflict
- 500 Internal Error

# 3.3.5 Update Node

The <code><ARM\_Configurator\_IP>/ARM/v1/topology/node/{id}</code> URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to update a specific node.

#### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/topology/node/{id}

#### **HTTP Method**

PUT

#### **Supported Content-Type**

application/json

#### Attributes

Attribute	Туре	Description
name	string	Name of the node.
transportType	string	Either HTTP or HTTPS
routingServerPolicy	String	ROUND_ROBIN, STICKY_PRIMARY, STICKY_LAST_AVALIABLE
useGeneralCredentials	Boolean	Either node should use general credentials
userName	String	userName for connecting to Node
routingServers:[  {  id:Integer,  priority:Integer,  status:String  }	-	Id – the ID of the routing server  Priority – the order in which the routering server are written to the node (asc order)  Status – AVAILABLE, UNAVAILABLE

- 200 OK
- 409 Conflict
- 500 Internal Error



# 3.3.6 Update Nodes Map Locations

The <ARM\_Configurator\_IP>/ARM/v1/topology/node/location URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to save the location of the node elements. In this event, the ARM Web interface will send a JSON object of all the nodes in the screen with their updated x and y coordinates.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/topology/node/location

#### **HTTP Method**

PUT

#### **Supported Content-Type**

application/json

#### Attributes

Attribute	Туре	Description
id	Integer	ID of the map locations.
х	Integer	X coordinate
у	Integer	Y coordinate

- 200 OK
- 409 Conflict
- 500 Internal Error

# 3.3.7 Update Routing Interface

The  $\ARM_Configurator_IP>/ARM/v1/topology/routingInterface/{id} URL$  when used with the PUT method provides the ability for the ARM Manager to send a request to the ARM Configurator to update a routing interface.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/topology/routingInterface/{id}

### **HTTP Method**

PUT

## **Supported Content-Type**

application/json

### Attributes

It MUST contain the following arguments:

Attribute	Туре	Description
name	String	Name of the routing interface.
controllpAddr	String	The IP address of the routing interface (SIP interface on the SBC).
tcpPort	Integer	TCP port name (0 for none)
udpPort	integer	UDP port name (0 for none)
tlsPort	integer	TLS port name (0 for none)

The combination of IP address and the 3 ports must be unique.

- 200 OK
- 409 Conflict
- 500 Internal Error



# 3.3.8 Update Clusters

The <code><ARM\_Configurator\_IP>/ARM/v1/topology/cluster</code> URL when used with the PUT method provides the ability for the ARM Manager to send a request to the ARM Configurator to update a Clusters interface.

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/topology/cluster

### **HTTP Method**

PUT

## **Supported Content-Type**

application/json

### **Attributes**

It MUST contain the following arguments:

Attribute	Туре	Description
id	String	Internal ID
х	Integer	X coordinate of the cluster
у	Integer	y coordinate of the cluster
nodes	[ String ]	List of UI internal node ids
name	String	The name of the cluster

- 200 OK
- 409 Conflict
- 500 Internal Error

# 3.3.9 Update Group

The <code><ARM\_Configurator\_IP>/ARM/v1/topology/group/{id}</code> URL when used with the PUT method provides the ability for the ARM Manager to send a request to the ARM Configurator to update a specific Group interface.

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/topology/group/{id}

## **HTTP Method**

PUT

## **Supported Content-Type**

application/json

### Attributes

It MUST contain the following arguments:

Attribute	Туре	Description
name	String	Group name: unique
elements	[ Integer ]	



# 3.3.10 Update Customer

The <code><ARM\_Configurator\_IP>/ARM/v1/topology/customer/{id}</code> URL when used with the PUT method provides the ability for the ARM Manager to send a request to the ARM Configurator to update a specific customer.

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/topology/customer/{id}

### **HTTP Method**

PUT

## **Supported Content-Type**

application/json

### **Attributes**

It MUST contain the following arguments except cacProfileId:

Attribute	Туре	Description
name	String	Customer name: unique
cacState	ENUM	operativeState:  0 = UNBLOCK  1 = BLOCK  2 = BLOCK_INCOMING  3 = BLOCK_OUTGOING
adminState	ENUM	adminState: 1 = LOCKED 2 = UNLOCKED
attributeGroups	[ Integer ]	Array of Attribute Groups ID's
sipHeaderName	ENUM	Header identification name sipHeaderName:  0 = CONTACT_HOST
sipHeaderValue	String	Header identification value
cacProfileId	Integer	CAC Profile ID

# 3.4 Topology Delete API

Note the following:

- The delete peer connection is only available when it is in locked status.
- The Peer connection can get to lock status after it is been deleted from the node itself.
- Delete node is only available if the node is locked.
- For multiple delete operations, multi response JSON is returned with the appropriate HTTP response code for each element.

### URL

```
<ARM_Configurator_IP>/ARM/v1/topology/peerCon/{id}
<ARM_Configurator_IP>/ARM/v1/topology/peerCon?filter=(id=id1;id2...)
<ARM_Configurator_IP>/ARM/v1/topology/connection/{id}
<ARM_Configurator_IP>/ARM/v1/topology/connection?filter=(id=id1;id 2...)
<ARM_Configurator_IP>/ARM/v1/topology/voippeer/{id}
<ARM_Configurator_IP>/ARM/v1/topology/voippeer?filter=(id=id1;id2...)
<ARM_Configurator_IP>/ARM/v1/topology/node/{id}
<ARM_Configurator_IP>/ARM/v1/topology/node?filter=(id=id1;id2...)
<ARM_Configurator_IP>/ARM/v1/topology/node?filter=(id=id1;id2...)
<ARM_Configurator_IP>/ARM/v1/topology/routingInterface/{id}
<ARM_Configurator_IP>/ARM/v1/topology/group/{id}
<ARM_Configurator_IP>/ARM/v1/topology/customer/{id}
```

- Note that delete peer connection is only available when it is in locked status. Peer connection can enter lock status after it has been deleted from the node itself. Peer connection can enter lock status after it has been deleted from the node itself. The delete action will only delete it from the database.
- Delete virtual peer connection is available even if it is not in locked status.
- Delete node is only available if node is locked
- For multiple delete operation Multi response JSON is returned with the appropriate HTTP response code for each element.
- Deleting routing interface will only work on routing interfaces associated with 3<sup>rd</sup> party devices

Where: For the suffix of each URL for update API, there is a {id} sign which represents the ID of the element in the database.

### **HTTP Method**

DELETE

### **Supported Content-Type**

application/json

- 200 OK
- 409 Conflict
- 500 Internal Error



# 3.5 Topology Actions API

# 3.5.1 Sync all Nodes Action

The <arm\_Configurator\_IP>/arm/v1/topology/sync URL when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to Sync all Nodes. This action forces the ARM server to read all configuration from all nodes in the system and update these values to the database. During this process, the server will push (if necessary) information such as connection details and servers details to a node. Note the following:

- If a filter is used only nodes with thee specified ids are synchronized.
- This action is an unsynchronized action which returns a unique job ID which the client may later ask for the action status with the assistance of the 7action status API (see Chapter 7).

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/topology/sync
<ARM Configurator IP>/ARM/v1/topology/sync?filter=(id=id1;id2...)

### **HTTP Method**

GET

## **Supported Content-Type**

application/json

- 202- If action has been accepted.
- 409- In case a previous Sync All Nodes action is in progress on the server; the server will not start a new action if a previous action is in progress.

# 3.5.2 Sync Node Action

The <code><ARM\_Configurator\_IP>/ARM/v1/topology/node/{id}/sync when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to synchronize a specific node.</code>

### **REST Resource**

<ARM Configurator IP>/ARM/v1/topology/node/{id}/sync

Where {id} is the database ID of the node. In this event, the ARM Configurator will perform synchronization between the current state of device and the node data in the database.

### **HTTP Method**

GET

### **Supported Content-Type**

application/json

## **HTTP Response**

200 OK



## 3.5.3 Lock Node Action

The  $\ARM_Configurator_IP>/ARM/v1/topology/node/{id}/lock$  URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to lock a node.

### **REST Resource**

```
<ARM_Configurator_IP>/ARM/v1/topology/node/{id}/lock
<ARM_Configurator_IP>/ARM/v1/topology/node/lock?filter=(id=id1;id2)
```

Where {id} is the database ID of the node.

For multiple lock operation Multi response, JSON is returned with the appropriate HTTP response code for each element.

### **HTTP Method**

PUT

### **Supported Content-Type**

application/json

### **Attributes**

Lock node request API MUST contain JSON data with the following argument:

Attribute	Туре	Description
lock	string	1 = lock 0 = unlock

### **HTTP Response**

200 OK

For multiple lock operation Multi response, the following additional codes may be returned:

- 409 Conflict (in case the operation is not allowed)
- 500 Internal Error

## 3.5.4 Lock Peer Connection Action

The  $ARM\_Configurator\_IP>/ARM/v1/topology/peerCon/{id}/lock$  URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to lock a Peer Connection.

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/topology/peerCon/{id}/lock
<ARM\_Configurator\_IP>/ARM/v1/topology/peerCon/lock?filter=(id=id1;
id2...)

{id} - database ID of the peer connection

For multiple lock operation Multi response, JSON is returned with the appropriate HTTP response code for each element.

### **HTTP Method**

PUT

### **Supported Content-Type**

application/json

### **Attributes**

Lock peer connection request API MUST contain JSON data with the following argument:

Attribute	Туре	Description
lock	string	3 = locked outgoing 2 = locked incoming 1 = lock 0 = unlock

- 200 OK
- 409 Conflict
- 500 Internal Error



# 3.5.5 Lock Router Action

The <code><ARM\_Configurator\_IP>/ARM/v1/topology/router/{id}/lock URL</code> when used with the PUT method provides the ability for the ARM Manager to send a request to the ARM Configurator to lock a router.

### **REST Resource**

PUT <ARM\_Configurator\_IP>/ARM/v1/topology/router/{id}/lock

{id} - database ID of the router

### Attributes

The Lock router request API MUST contain JSON data of the following argument:

Attribute	Туре	Description
lock	string	1 = lock 0 = unlock

- 200 OK
- 409 Conflict
- 500 Internal Error

Developer's Guide 3. Topology Rest API

# 3.5.6 Lock Customer Action

The <code> <ARM\_Configurator\_IP>/ARM/v1/topology/customer/{id}/lock URL when used with the PUT method provides the ability for the ARM Manager to send a request to the ARM Configurator to lock a specific customer.</code>

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/topology/customer/{id}/lock

{id} - database ID of the customer

## **HTTP Method**

PUT

# **Supported Content-Type**

application/json

### Attributes

Lock customer request API MUST contain JSON data of the following argument:

Attribute	Туре	Description
lock	ENUM	0 = unlock 1 = lock 2 = lockIncoming 3 = lockOutgoing

### **HTTP Response**

200 OK



# 3.5.7 Lock Multiple Customers Action

The <code> <ARM\_Configurator\_IP>/ARM/v1/topology/customer/{id}/lock URL when used with the PUT method provides the ability for the ARM Manager to send a request to the ARM Configurator to lock multiple customers.</code>

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/topology/customer/lock?filter=(id=1;2
;3...)

{id} - database ID of the customer

### **HTTP Method**

PUT

## **Supported Content-Type**

application/json

### **Attributes**

Lock customer request API MUST contain JSON data of the following argument:

Attribute	Туре	Description
lock	ENUM	0 = unlock 1 = lock 2 = lockIncoming 3 = lockOutgoing

### **HTTP Response**

200 OK

## 3.5.8 Detach Peer Connection Action

The  $\ARM_Configurator_IP>/ARM/v1/topology/peerCon/{id}/detach$  URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to detach a Peer Connection.

### **REST Resource**

<ARM Configurator\_IP>/ARM/v1/topology/peerCon/{id}/detach

{id} - database ID of the peer connection

### HTTP Method

PUT

### **Attributes**

Lock node request API MUST contain JSON data of the following argument:

Attribute	Туре	Description
name	string	The name of the created VP, must be unique

# HTTP Response

- 200 OK
- 409 Conflict
- 500 Internal Error

# 3.5.9 Configure Node

### **REST Resource**

GET <ARM Configurator IP>/ARM/v1/topology/node/{id}/configure

{id} - database ID of the node

If single sign on operation is supported returns url with token (logged in to node), otherwise returns the url of the node (node's login page).

### **HTTP Method**

GET

- 200 OK
- 409 Conflict
- 500 Internal Error



This page is intentionally left blank.

# 4 Routing API

This chapter describes the REST API resources for the ARM routing. The following APIs are described:

- Get API
- Routing Create API
- Routing Update API
- Routing Delete API
- Test Route API
- Time-based Routing (TBR) API
- Attribute Group API

# 4.1 Get API

The  $\ARM\_Configurator\_IP>/ARM/v1/routing/<ARM\_attribute> URL when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve a route.$ 

### **REST Resource**

```
<ARM_Configurator_IP>/ARM/v1/routing/<ARM_attribute>
<ARM Configurator IP>/ARM/v1/routing/<ARM attribute>/{id}
```

#### Where:

- {id} requests a specific ID of a specific attribute (listed in the table below). In case of the Routing Rule attribute, requests for all Routing Rules will only be supported at the Group level.
- <ARM\_attribute> requests all of the ids of the specified attribute (listed in the table below).

### **HTTP Method**

GET

## **Supported Content-Type**

application/json

### **Attributes**

The ARM Configurator must respond to the Get request with JSON data that includes the request URI attribute. If the ID is not specified in the GET request, URI JSON data MUST contain an array of all specified elements defined in the database for the attribute.

The following attributes MUST be included:

Attribute	Туре	Description
routingRule	{	Enums:
	id: Integer	RoutingRuleAttrType:
	name: String	0 = PREFIX
		1 = HOST_NAME



Attribute	Туре	Description
	id: Integer ] dstUserGroup: [ id: Integer ] actions: [ {     priority : Integer     nodeld: Integer     peerConnectionId: Integer     voipPeerId: Integer     srcNormalizationGroupId: Integer     destNormalizationGroupId: Integer     weight:Integer     viaNodes:     [         Id: Integer     ]     discard: Boolean     sipReason: Integer } ]	
routingGroup	ARRAY OF: [	adminState  0 = UNLOCKED  1 = LOCKED
sipResponseAction	ARRAY OF:	



Attribute	Туре	Description
	<pre>id: int     sipResponseNumber: int     sipResponseDescription: String     reroute: Boolean } </pre>	

- 200 OK
- 204 No Content Response

# 4.1.1 Get Filter

You can use a filter for specific requests. Filters should be added to the suffix of the URL, for example:

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/routing/routingRule?filter=(adminStat
e=1)
<ARM\_Configurator\_IP>/ARM/v1/routing/routingGroup?filter=(quality=
2)

### **HTTP Method**

GET

### **Supported Content-Type**

application/json

### **Attributes**

Filter	Available for These Requests	Description	
adminState	routingRule	Node ID= <value></value>	
testMode	routingRule	Connection ID= <value></value>	
quality	routingRule	User Group ID= <value></value>	
isDiscard	routingRule	Equals (=)	
rrName	routingRule	Contains (~)	
rrGroupName	routingRule	Contains (~)	
isRegisteredUsers	routingRule	Equals (=)	
isContinueWithNodeTables	routingRule	Equals (=)	
requestType	routingRule	Equals (=)	
userGroupId	routingRule	Equals (=)	
prefixGroupId	routingRule	Equals (=)	
searchString	routingGroup	Contains (~) – searches in most of the fields of the group and the rules inside the group (node name, peer connection name, voippeer name, prefix, host etc.)	

- 200 OK if at least one resource is found.
- 204 No Content Response



# 4.2 Routing Create API

This section describes the Routing Create API.

# 4.2.1 Routing Group Create API

The ARM\_Configurator\_IP>/ARM/v1/routing/routingGroup URL when used with the POST method, provides the ability for the ARM Manager to send a request to the ARM Configurator to create a Routing Group.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/routing/routingGroup

### **HTTP Method**

POST

### **Supported Content-Type**

application/json

### **Attributes**

The request MUST consist of the following arguments:

Attribute	Туре	Description
name	String	The name of the Routing Group (must be unique).
adminState	adminState	adminState:  0 = UNLOCKED  1 = LOCKED
prevRRGroupId	Integer	prevRRGroupId indicates the previous routing group prevRRGroupId = -1 if first in the list
nextRRGroupId	Integer	nextRRGroupId indicates the next routing group nextRRGroupId = -1 if last in the list
tbrConditionsIds	List of Integers	The ids of the condition to attach to the Routing Rule.

- 201 Created The ARM Configurator responds to the request if completed successfully and the corresponding group is sent.
  - In case there was recalculation of all priorities in the database (the ARM user has changed the order of the Routing Groups), the Created group is returned with -1 priority value.
- 409 Conflict in case the operation is not allowed.
- 500 Internal Error

# 4.2.2 Routing Rule Create API

The <code><ARM\_Configurator\_IP>/ARM/v1/routing/routingRule</code> URL when used with the POST method, provides the ability for the ARM Manager to send a request to the ARM Configurator to create a routing rule.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/routing/routingRule

### **HTTP Method**

POST

## **Supported Content-Type**

application/json

### Attributes

The request MUST consist of the following arguments:

Attribute	Туре	Description
name	String	The name of the Routing Rule (must be unique).
adminState	adminState	adminState  0 = UNLOCKED  1 = LOCKED
prevRRId	Integer	prevRRId stands for previous routing rule prevRRId = -1 if first in the list
nextRRId	Integer	nextRRId stands for next routing rule nextRRId = -1 if last in the list
rrGroupId	Integer	Routing rule group ID
sourceNodes	[ id : Integer ]	ID of the source node (Optional)
sourcePcons	[ id: Integer ]	ID of the sourcePcons (Optional)
sourceRRAttr	{   attributes: [     {      type:     RoutingRuleAttrTyp     e (enum)      value: String     } ],   attributeGroups:	Optional



Attribute	Туре	Description
	[ Integer ] }	
destRRAttr	{   attributes: [     {      type:      RoutingRuleAttrTyp      e (enum)      value: String     }   ],   attributeGroups:   [   Integer   ] }	Optional
sourceUserGroups	[ id: Integer ]	Optional
dstUserGroup	[ id: Integer ]	Optional
actions	[	* priority will be used also for load balancing  * At least one action must be present  * peerConnectionId and viaNodes are Optional     *must contain nodeId or voipPeerid  * peer connection can appear only with node  * weight – used when there are actions with the same priority, default 50  srcNormalizationGroupId / destNormalizationGroupId (Optional) – The normalization Group that will be done on the action isEquallyBalanced - whether all the actions in the same priority group should be load balanced, if should have the same value for all of the actions in the priority group. If its true the weight is ignored.

Attribute	Туре	Description
	isEquallyBalanced:B oolean	sipReason - Defines the SIP error code that will be presented in the SIP message when the message will be discarded     The value should be between 400-699
	routingAttempts:Integ er	Or null incase the sip reason is taken from error code of the SIP message
	sipReason:Integer discard: Boolean	Discard - Defines whether this action should discard the call or not, if this field is set to true, the action must be with the lowest priority and there must not be another action with the
	viaNodes: [ Id:	same priority (load balancing).
	Integer ]	
	discard: Boolean sipReason: Integer }	
sipReason	Integer	Defines the SIP error code that is displayed in the SIP message when a call is disconnected (when 'discard' attribute is true)
		<ul> <li>The value should be between 400-699.</li> <li>0 in case 'discard' attribute is disabled i.e. this attribute is only relevant when discard attribute is 'true'. When it is true then 'sipReason' is mandatory.</li> </ul>
discard	Boolean	Defines whether the call should be disconnected.
tbrConditionsIds	List of Integers	The ids of the condition to attach to the Routing Rule Group.
isEmergency	Boolean	Indicates if the rule is prioritized
isTrigger3xx	Boolean	-
isTriggerRefer	Boolean	-
isTriggerInitialOnly	Boolean	-
isTriggerBrokenConn ection	Boolean	-
isTriggerFaxRerouting	Boolean	-
privacy	ENUM	Defines which privacy strategy rule to use:



Attribute	Туре	Description
		TRANSPARENT,TRANSPARENT_WITH_PRIVA CY_ID, ANONYMOUS_CALLER, IDENTIFY_CALLER
eventOnMatch	Boolean	-
sipHeaders	{ name:String value:String }	Match specific headers, name is the SIP header, value is the value to match
sourceTopologyGroup s	[ Integer ]	Indicates the source Topology Groups
isRegisteredUsers	Boolean	Enables the Registered Users feature for operators to route calls to SBC registered users
minSecureLogix	Integer	Used for Security Based Routing. Defines the minimum Security call score option for the 'SecureLogix' web service. The Routing Rule uses the score returned from the 'SecureLogix' web service as part of the match.
		Note: this service must be enabled in the ARM GUI "Security call score" for this setting to take effect. In addition, both this attribute and maxSecureLogix below must be configured, otherwise an error is returned.
maxSecureLogix	Integer	Used for Security Based Routing. Defines the minimum Security call score option for the 'SecureLogix' web service. The Routing Rule uses the score returned from the 'SecureLogix' web service as part of the match.  Note: this service must be enabled in the ARM GUI "Security call score" for this setting to take effect. In addition, both this attribute and minSecureLogix above must be configured, otherwise an error is returned.
tags	[ RoutingRuleTag ]	RoutingRuleTag: {     id: Integer,     tag: ActionCallSetupFields,     value: String,     rrld: Integer }  ActionCallSetupFields:     0 = SOURCE_URI_USER     1 = SOURCE_URI_HOST     2 = DEST_URI_USER     3 = DEST_URI_HOST     4 = DEST_IP_ADDR     5 = DEST_PORT     6 = DEST_PROTOCOL

Attribute	Туре	Description
		7 = USER_CREDENTIALS_USER_NAME 8 = USER_CREDENTIALS_PASSWORD 9 = P_ASSERTED_IDENTITY_DISPLAY_NAME 10 = P_ASSERTED_IDENTITY_USER 11 = P_ASSERTED_IDENTITY_HOST 12 = TAG_1 13 = TAG_2 14 = TAG_3 15 = CREDENTIALS 16 = DISCARD_CREDENTIALS
requestType	ENUM	0 = CALL 1 = REGISTER
sourceCustomers	[ Integer ]	Customer ids
destCustomers	[ Integer ]	Customer ids
allSourceCustomers	Boolean	
allDestCustomers	Boolean	

- 201 Created
- 409 Conflict
- 500 Internal Error



# 4.2.3 SIP Response Action Create

The URL <code><ARM\_Configurator\_IP>/ARM/v1/routing/sipResponseAction</code> when used with the POST method provides the ability for the ARM Manager to send a request to the ARM Configurator to create a SIP Response action.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/routing/sipResponseAction

### **HTTP Method**

POST

## **Supported Content-Type**

application/json

### **Attributes**

The request MUST consist of the following arguments:

Attribute	Туре	Description
sipResponseNumber	Int	The response number must be unique.
sipResponseDescription	String	The text description of the SIP response.
reroute	Boolean	Mandatory

- 201 Created
- 409 Conflict
- 500 Internal Error

# 4.3 Routing Update API

This section describes the Routing Update API.

# 4.3.1 Routing Rule Update API

The <code><ARM\_Configurator\_IP>/ARM/v1/routing/routingRule/{id}URL</code> when used with the PUT method provides the ability for the ARM Manager to send a request to the ARM Configurator to update a routing rule.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/routing/routingRule/{id}

Where {id} is the ID of the element in the database.

### **HTTP Method**

PUT

## **Supported Content-Type**

application/json

### **Attributes**

The request should contain the following elements:

Attribute	Туре	Description
name	String	The name of the Routing Rule (must be unique for the specific Routing Rule group).
adminState	adminState	adminState:  0 = UNLOCKED  1 = LOCKED
prevRRId	Integer	prevRRId is the previous routing rule prevRRId = -1 if first in the list.  Optional – if not sent, nextRRId will also not be checked.
nextRRId	Integer	nextRRId is the next routing rule nextRRId = -1 if last in the list. Optional
sourceNodes	[ id : Integer ]	The ID of the source node.
sourcePcons	[ id: Integer ]	The ID of the sourcePcons.
sourceRRAttr	{ attributes: [	The source Routing Rule attributes.



Attribute	Туре	Description
	{   type: RoutingRuleAttrType (enum)   value: String   } ], attributeGroups: [ Integer ] }	
destRRAttr	{   attributes: [     {      type:      RoutingRuleAttrType (enum)      value: String     }   ],   attributeGroups:   [   Integer   ] }	The destination Routing Rule attributes.
sourceUserGroups	[ id: Integer ]	The ID of the source User Groups.
dstUserGroups	[ id: Integer ]	The ID of the destination User Group
actions	[     nodeld: Integer     priority: Integer     peerConnectionId: Integer     voipPeerId: Integer     srcNormalizationGroupId:     Integer     destNormalizationGroupId:     Integer     weight:Integer     isEquallyBalanced:Boolea     n	Mandatory (at least one)  srcNormalizationGroupId / destNormalizationGroupId (Optional) — The normalization Group that will be applied to the action  * must contain nodeId or voipPeerid * peer connection can appear only with node

Attribute	Туре	Description
	routingAttempts:Integer	
	sipReason:Integer	
	discard: Boolean	
	viaNodes:	
	ld: Integer	
	]	
	}	
	topologyGroupId: Integer	
	attemptsInTopologyGroup: Integer	
	registeredUsers: Boolean	
	continueWithNodeInternal Tables: Boolean	
	destTypeRequestUri: Boolean	
	srcNormalizationFromHea der: Boolean	
	srcNormalizationPAIHead er: Boolean	
	srcNormalizationPPIHead er: Boolean	
	customerNormalizationS IPHeader: Boolean	
	}	
	]	
discard	Boolean	Defines whether the call should be disconnected.
sipReason	<ul><li>Integer</li><li>The value should be between 400-699</li><li>0 in case discard is disabled</li></ul>	Defines the SIP error code that is displayed in the SIP message when a call is disconnected (when 'discard' attribute is true)  The value should be between 400-699.  O in case 'discard' attribute is disabled
		i.e. this attribute is only relevant when discard attribute is 'true'. When it is true then 'sipReason' is mandatory.
tbrConditionsIds	List of Integers	The ids of the condition to attach to the Routing Rule Group.
quality	Enum	The quality of the route that will be chosen if quality based routing is enabled  FAIR GOOD



Attribute	Туре	Description	
isTrigger3xx	Boolean	-	
isTriggerRefer	Boolean	-	
isTriggerInitialOnly	Boolean	-	
isTriggerBrokenCon nection	Boolean	-	
isTriggerFaxRerouti ng	Boolean	-	
privacy	ENUM	Defines which privacy strategy should be used if the rule is matched: TRANSPARENT,TRANSPARENT_WITH _PRIVACY_ID, ANONYMOUS_CALLER, IDENTIFY_CALLER	
eventOnMatch	Boolean	-	
sipHeaders	{     name:String     value:String }	Match specific headers, name is the SIP header, value is the value to match	
sourceTopologyGro ups	[Integer]	The Topology Group ID of the Routing rule.	
isRegisteredUsers	Boolean	Enables the Registered Users feature for operators to route calls to SBC registered users.	
minSecureLogix	Integer	Used for Security Based Routing. Defines the minimum Security call score option for the 'SecureLogix' web service. The Routing Rule uses the score returned from the 'SecureLogix' web service as part of the match.	
		Note: this service must be enabled in the ARM GUI "Security call score" for this setting to take effect. In addition, both this attribute and maxSecureLogix below must be configured, otherwise an error is returned.	
maxSecureLogix	Integer	Used for Security Based Routing. Defines the maximum Security call score option only if the 'SecureLogix' web service is used. Once enabled, the Routing Rule will use the score returned from the 'SecureLogix' web service as part of the match.	
		Note: this service must be enabled in the ARM GUI "Security call score" for this setting to take effect. In addition, both this attribute and minSecureLogix above must be configured, otherwise an error is returned.	
tags	[ RoutingRuleTag ]	RoutingRuleTag:	

Attribute	Туре	Description
		<pre>{   id: Integer,   tag: ActionCallSetupFields,   value: String,   rrld: Integer }</pre>
requestType	ENUM	0 = CALL 1 = REGISTER
sourceCustomers	[ Integer ]	Customer ids
destCustomers	[Integer]	Customer ids
allSourceCustomers	Boolean	
allDestCustomers	Boolean	

- 200 OK
- 409 Conflict (in case the operation is not allowed)
- 500 Internal Server Error



# 4.3.2 Routing Group Update API

The <code><ARM\_Configurator\_IP>/ARM/v1/routing/routingGroup/{id}</code> URL when used with the PUT method provides the ability for the ARM Manager to send a request to the ARM Configurator to update a Routing Group.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/routing/routingGroup/{id}

Where {id} is the ID of the element in the database.

### HTTP Method

PUT

# **Supported Content-Type**

application/json

### **Attributes**

The request should contain the following elements:

Attribute	Туре	Description
adminState	adminState	The adminState of the routing group:  0 = UNLOCKED  1 = LOCKED
name	String	The name of the routing group. This name must be unique.
prevRRId	Integer	prevRRId indicates the previous routing rule prevRRId = -1 if first Note: if not sent, this implies that the location of the rule has not changed and therefore nextRRId will also not be checked.  If a new rule is added to table, -1
nextRRId	Integer	nextRRId indicates the next routing rule nextRRId = -1 if last
tbrConditionsIds	List of Integers	The ids of the condition to attach to the Routing Rule Group.

### Response

Corresponding Routing Rule Group will be sent. In case there was recalculation of all priorities for the rules in the Database (the ARM User changed the order of the Routing Groups) the Created group will be returned with -1 priority value.

# 4.3.3 SIP Response Action Update API

The  $\ARM_Configurator_IP>/ARM/v1/routing/sipResponseAction/{id} URL$  when used with the PUT method, it provides the ability for the ARM Manager to send a request to the ARM Configurator to update a SIP response action.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/routing/sipResponseAction/{id}

Where {id} is the ID of the element in the database.

### **HTTP Method**

PUT

# **Supported Content-Type**

application/json

### **Attributes**

The request should contain the following elements:

Attribute	Туре	Description
sipResponseNumber	Int	The SIP Response Number (must be unique).
sipResponseDescription	String The description of the SIP response.	
reroute	Boolean	Mandatory

- 200 OK
- 409 Conflict in case the operation was not allowed.
- 500 Internal Error



# 4.4 Routing Delete API

You can send a request to the ARM Configurator to delete a routing rule, a routing group or a SIP Response action.

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/routing/routingRule/{id}
<ARM\_Configurator\_IP>/ARM/v1/routing/routingGroup/{id}
<ARM Configurator IP>/ARM/v1/routing/sipResponseAction/{id}

Where {id} is the ID of the element in the database.

### **HTTP Method**

DELETE

### **Supported Content-Type**

application/json

- 200 OK
- 409 Conflict (in case the operation is not allowed)
- 500 Internal Server Error

# 4.5 Test Route API

The <ARM\_Configurator\_IP>/ARM/v1/routing/testRoute URL when used with the POST method provides the ability for the ARM Manager to send a request to the ARM Configurator to update a test route.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/routing/testRoute

### **HTTP Method**

POST

## **Supported Content-Type**

application/json

## **Request Attributes**

The request should contain the following elements:

Attribute	Туре	Description	
srcPeerConnection	Integer	The ID of the peer connection.	
srcNode	Integer	The ID of the srcNode.	
maxRoutes	Integer	The maximum number of routes to find. When this attribute is not contained in the request, the default value 6 applies.	
maxRoutesPerDestin ation	Integer	The maximum number of routes per destination to find. When this attribute is not contained in the request, the default value 2 applies.	
srcUser	string	The name of the user of the call source.	
srcHost	string	The name of the source host (optional).	
destUser	string	The name of the user of the call destination.	
destHost	string	The name of the host of the call destination (optional).	
routerId	Integer	(Optional) The ID of the router that will respond to the route request	
isTrigger3xx	Boolean	Mark the test route request as if it was a 3XX response	
isTriggerRefer	Boolean	Mark the test route request as if it was a referred call.	
isTriggerInitialOnly	Boolean	-	
isTriggerBrokenConn ection	Boolean	-	



Attribute	Туре	Description
isTriggerFaxReroutin g	Boolean	-
headers	ARRAY OF: [	<ul> <li>Name – for now only "Contact" will be supported. It should be a unique name in this array (optional). name is enum (current with only one value "Contact").</li> <li>Value – as a real Contact header.         For example: <sip:401@10.7.2.17> or <sip:401@10.7.2.17:5060> or <sip:401@moshebe.audiocodes.com> or <sip:moshecell@moshebe.audiocodes.com:6061></sip:moshecell@moshebe.audiocodes.com:6061></sip:401@moshebe.audiocodes.com></sip:401@10.7.2.17:5060></sip:401@10.7.2.17></li> <li>GUI validations:         The header should be a unique name in this array. It can be added from IPGroup Pcon (not TrunkGroup). The Name and value are not null or empty string.</li> </ul>

# Response Attributes

The response should contain the following attributes:

Attribute	Туре	Description
srcNode	Integer	The source node ID.
srcPeerConnection	Integer	The peer connection ID.
httpResponse	Integer	The HTTP response code.
description	String	The description of the routing manipulation list.
preRouteManipulationsList	ARRAY OF:[{     originalValue:String     manipulatedValue:String     manipulatedEntity:String     isChanged:Boolean manipulationsList:[{     originalValue:String     manipulatedValue:String     manipulatingEntity:String     manipulatingEntityUrl:     String     manipulatingEntityName:     String	<ul> <li>ManipulatingEnti ty (optional)- the entity from ARM data base/GUI perspective which tracked and might change the ManipulatedEntit y.</li> <li>ManipulatedEntit y (optional)- the entity that is tracked and may change.</li> </ul>

Attribute	Туре	Description
	usingManipulatingEntity:S tring usingManipulatingEntityUr I: String usingManipulatingEntityN ame:String description:String isChanged:Boolean }] }]	<ul> <li>originalValue:         the value of the         manipulated         entity prior to         manipulation (in         the case of         user/password/d         estIP), these         entities may be         optional as well.</li> <li>Note: When the         ManipulatingEnti         ty is a         'RoutingRuleActi         on', there is no         URL.</li> </ul>
paths	ARRAY OF:  [{      destNode:Integer     destPeerConnection:Integer     routingRuleAction:Integer     routingRuleID:Integer  edges:[{         connSrcNode:Integer         connDestNode:Integer         connectionId:Integer }]  pathRouteManipulationsList:[{         originalValue:String         manipulatedValue:String         manipulatedEntity:String         isChanged:Boolean  manipulationsList:[{         originalValue:String         manipulatedValue:String         manipulatedValue:String         manipulatingEntity:String  String  string  usingManipulatingEntityName: String  usingManipulatingEntityUr l: String  usingManipulatingEntityUr l: String  description:String  description:String	<ul> <li>ManipulatingEnti ty (optional)- the entity from ARM data base/GUI perspective which tracked and might change the ManipulatedEntit y.</li> <li>ManipulatedEntit y (optional)- the entity that is tracked and might change.</li> <li>originalValue: the value of the manipulated entity prior to manipulation (in the case of user/password/d estIP), these entities may be optional as well.</li> <li>Note: when the ManipulatingEnti ty is a RoutingRuleActi on, it contains a RoutingRule URL.</li> <li>The RoutingRuleActi onld is attached per path as well.</li> </ul>



Attribute	Туре	Description
	isChanged:Boolean }] }] ]	
discardingByRoutingRule	Integer	The ID of the routing rule which discards the call1 if there is no such rule.
preRouteManipulationsList	RouteManipulations	
discardingByRrName	String	
discardingByRrGroupName	String	
continueWithNodeInternalTablesByRo utingRule	Integer	
continueWithNodeInternalTablesgByR rName	String	
continueWithNodeInternalTablesByRr GroupName	String	
routerId	Integer	
incomingCustomerId	Integer	
outgoingCustomerId	Integer	
incomingCustomerName	String	
outgoingCustomerName	String	

- 200 OK
- 409 Conflict (in case the operation is not allowed)
- 500 Internal Server Error

### **Other Information**

- preRouteManipulationsList and pathRouteManipulationsList:
  - ManipulatedEntity means which entity will be tracked and might change.
  - ManipulatedEntity values:
    - SOURCE\_URI\_USER
    - SOURCE\_URI\_HOST
    - DEST\_URI\_USER
    - DEST URI HOST
    - DEST\_IP\_ADDR
    - DEST\_PORT
    - DEST\_PROTOCOL
    - USER\_CREDENTIALS\_USER\_NAME
    - USER\_CREDENTIALS\_PASSWORD
  - Only tracked will be added to routeManipulationsList.
  - isChanged will be set to true if one of the isChanged in manipulationsList is true.
- ManipulatingEntity means which entity from ARM data base/GUI perspective tracked and might change the ManipulatedEntity.
  - ManipulatingEntity values:
    - ROUTING\_INCOMING\_MANIPULATION
    - PCON
    - CALL\_SETUP\_RULE
    - ROUTING RULE ACTION
    - NORMANIZATION GROUP
  - usingManipulatingEntity and usingManipulatingEntityId are Optional.



preRouteManipulationsList and pathRouteManipulationsList examples:

**Example 1:** if Pcon 1 with NormalizationGroup 2 and Call Setup Rule 3 and Routing Rule Action 4 with NormalizationGroup 5 changed sourceUriUser:

```
preRouteManipulationsList:{
         originalValue:12
         manipulatedValue:56
         manipulatedEntity:SOURCE URI USER
         isChanged:true
         manipulationsList:[{
                 originalValue:12
                 manipulatedValue:34
                 manipulatingEntity: PCON
                 manipulatingEntityId:1
                 usingManipulatingEntity:NORMANIZATION GROUP
                 usingManipulatingEntityId:2
                 description:
                 isChanged:true
                 },
                 originalValue:34
                 manipulatedValue:56
                 manipulatingEntity: CALL SETUP RULE
                 manipulatingEntityId:3
                 description:
                 isChanged:true
                 } ]
paths =[{
          pathRouteManipulationsList:[{
                 afrerPreRouteValue:String
                          originalValue:56
                          manipulatedValue:78
                          manipulatingEntity: ROUTING RULE ACTION
                          manipulatingEntityId:4
                          usingManipulatingEntity:NORMANIZATION GROUP
                          usingManipulatingEntityId:5
                          description:
                          isChanged:true
                    } ]
```

**Example 2**: if RoutingIncomingNormalization (it doesn't have really an index so we set it to "-1") with NormalizationGroup 2 and Call Setup Rule 3 and Routing Rule Action 4 with NormalizationGroup 5 changed sourceUriUser:

```
preRouteManipulationsList:{
       originalValue:12
       manipulatedValue:56
       manipulatedEntity:SOURCE URI USER
       isChanged:true
       manipulationsList:[{
                 originalValue:12
                 manipulatedValue:34
                 manipulatingEntity: ROUTING INCOMING MANIPULATION
                manipulatingEntityId:-1
                usingManipulatingEntity:NORMANIZATION GROUP
                usingManipulatingEntityId:2
                description:
                isChanged:true
                },
                {
                originalValue:34
                manipulatedValue:56
                manipulatingEntity:CALL SETUP RULE
                manipulatingEntityId:3
               description:
               isChanged:true
               } ]
paths =[{
         pathRouteManipulationsList:[{
               originalValue:56
               manipulatedValue:78
               manipulatingEntity: ROUTING RULE ACTION
               manipulatingEntityId:4
               usingManipulatingEntity:NORMANIZATION GROUP
               usingManipulatingEntityId:5
               description:
               isChanged:true
               }
               1
        } ]
```



# 4.6 Time-based Routing (TBR) API

This section describes the Time-based Routing API.

## 4.6.1 TBR Conditions Create API

The <code><ARM\_Configurator\_IP>/ARM/v1/routing/condition/tbr</code> URL when used with the POST method, provides the ability for the ARM Manager to send a request to the ARM Configurator to create conditions for Time-based routing.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/routing/condition/tbr

### **HTTP Method**

POST

## **Supported Content-Type**

application/json

### **Attributes**

The request should contain the following attributes:

Attribute	Туре	Description
TimeCondition	<pre>{     "id": Integer,     "name" String,     "days": [         "day": Day         "startTime": Time (String),         "endTime": Time (String),     ],      "startDateTime": DateTime (String),     "endDateTime": DateTime (String)     "startDay": Day,     "endDay:" Day,     "type": Enum (Integer) }</pre>	Enum DAYS: SUN, MON, TUE, WED, THU, FRI, SAT startTime and endTime are optional in case the type is WEEKLY or PERIOD. If they are not sent, the condition will be for a full day (not sent equals both of them being null), In type DAILY the days should have all the days of the week, and startTime and endTime are must, and must be the same time for all days. In type RANGE days should have only two days, the start day with startTime and end day with endTime. Example of the time format: 12:12:21.000 startDateTime and endDateTime will be ignored unless the type is PERIOD startDay and endDay will be ignored unless type is RANGE startDateTime and endDateTime should be in the same format as defined by Alex, for example: 2015-11-12T14:21:19.000Z Enum Type: DAILY, WEEKLY, PERIOD or RANGE

- 200 OK if no error occurred.
- 409 Conflict if an error occurred.

# 4.6.2 TBR Condition Update API

The <code><ARM\_Configurator\_IP>/ARM/v1/routing/condition/tbr/{id}</code> URL when used with the PUT method provides the ability for the ARM Manager to send a request to the ARM Configurator to update a TBR condition.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/routing/condition/tbr/{id}

## **HTTP Method**

PUT

## **Supported Content-Type**

application/json

### Attributes

Attributes		
Attribute	Туре	Description
TimeCondition		Enum DAYS:
	{	SUN, MON, TUE, WED, THU, FRI, SAT
	"id":Integer, "name" String,	startTime and endTime are optional in case the type is WEEKLY or PERIOD.
	"days" : [  "day": Day  "startTime": Time	If they are not sent, the condition will be for a full day (not being sent is equivelant to both of them being set to null).
	(String), "endTime": Time (String),	In type DAILY, the days should include all the days of the week, startTime and endTime are mandatory, and must be the same time for all days.
	],  "startDateTime":  DateTime (String),	In type RANGE, days should be set to only two days, the start day with startTime and end day with endTime.
	"endDateTime": DateTime (String)	Example of the time format: 12:12:21.000 startDateTime and endDateTime will be ignored unless the type is PERIOD
	"startDay": Day, "endDay:" Day,	startDay and endDay will be ignored unless type is RANGE.
	"type": Enum (Integer) }	startDateTime and endDateTime should be in the same format as defined by Alex, for example: 2015-11-12T14:21:19.000Z Enum Type: DAILY, WEEKLY, PERIOD or RANGE

- 200 OK if no error occurred
- 409 Conflict if an error occurred



## 4.6.3 TBR Condition Delete API

The  $\ARM_Configurator_IP>/ARM/v1/routing/condition/tbr/{id URL provides}$  the ability for the ARM Manager to send a request to the ARM Configurator to delete a TBR condition.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/routing/condition/tbr/{id}

Where {id} is the ID of the element in the database.

### HTTP Method

DELETE

## **Supported Content-Type**

application/json

## **HTTP Response**

- 200 OK if no error occurred.
- 409 Conflict if an error occurred.

Note: Conditions that are attached to Routing Rule Groups or Routing Rules cannot be deleted.

# 4.7 Attribute Group API

This section describes the URLs for Attribute Groups.

## 4.7.1 Attribute Group Get API

The <code><ARM\_Configurator\_IP>/ARM/v1/routing/attributeGroup URL</code> when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve an Attribute Group.

## **REST Resource**

```
<ARM_Configurator_IP>/ARM/v1/routing/attributeGroup
<ARM_Configurator_IP>/ARM/v1/routing/attributeGroup/{id}
```

### **HTTP Method**

GET

## **Supported Content-Type**

application/json

#### Attributes

Attribute	Туре	Description
attrGroup	{     "id" : Integer     "name" String,     "values" : [         String     ],     "type": ENUM (String), }	Name – must be unique Type: 0 = PREFIX 1 = HOST_NAME
attrGroups	[ { attrGroup }	Name – must be unique Type: 0 = PREFIX 1 = HOST_NAME

- 200 OK if no error occurred.
- 409 Conflict if an error occurred.



## 4.7.2 Attribute Group Create API

The <ARM\_Configurator\_IP>/ARM/v1/routing/attributeGroup URL when used with the PUT method provides the ability for the ARM Manager to send a request to the ARM Configurator to create an Attribute Group.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/routing/attributeGroup

## **HTTP Method**

PUT

## **Supported Content-Type**

application/json

## Attributes

Attribute	Туре	Description
attrGroup	{     "name" String,     "values" : [         String ],     "type": ENUM (String), }	Name – must be unique type: 0 = PREFIX 1 = HOST_NAME

- 200 OK if no error occurred.
- 409 Conflict if an error occurred.

# 4.7.3 Attribute Group Update API

The <code><ARM\_Configurator\_IP>/ARM/v1/routing/attributeGroup/{id}</code> URL when used with the PUT method provides the ability for the ARM Manager to send a request to the ARM Configurator to update an Attribute Group.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/routing/attributeGroup/{id}

## **HTTP Method**

PUT

## **Supported Content-Type**

application/json

## Attribute

Attribute	Туре	Description
attrGroup	{     "name" String,     "values" : [         String ],     "type": ENUM (String), }	Name – must be unique type: 0 = PREFIX 1 = HOST_NAME

- 200 OK if no error occurred.
- 409 Conflict if an error occurred.



## 4.7.4 Attribute Group Add\Remove Attributes API

The <code><ARM\_Configurator\_IP>/ARM/v1/routing/attributeGroup/{id}</code> URL when used with the PATCH methods provides the ability for the ARM Manager to send a request to the ARM Configurator to update specific attributes within an attribute group without setting the entire resource.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/routing/attributeGroup/{id}

### **HTTP Method**

PATCH

#### **Attribute**

With the following JSON:

Attribute	Туре	Description
attrGroup	{     "add": [ String ],     "remove": [ String ] }	Add and remove values

- 200 OK if no error occurred.
- 409 Conflict if an error occurred.

## 4.7.5 Attribute Group Delete API

The <ARM\_Configurator\_IP>/ARM/v1/routing/attributeGroup/{id} when used with the DELETE method provides the ability for the ARM Manager to send a request to the ARM Configurator to delete an Attribute Group.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/routing/attributeGroup/{id}

### **HTTP Method**

DELETE

## **Supported Content-Type**

application/json

## **HTTP Response**

- 200 OK if no error occurred.
- 409 Conflict if an error occurred.

**Note:** An Attribute Group cannot be deleted when it contains conditions that are attached to Routing Rule Groups or Routing Rules.



## 4.7.6 Attribute Group Multiple Delete API

### The

<ARM\_Configurator\_IP>/ARM/v1/routing/attributeGroup?filter=(id=1;2;

3) URL when used with the DELETE methods provides the ability for the ARM Manager to send a request to the ARM Configurator to delete multiple Attribute Groups.

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/routing/attributeGroup?filter=(id=1;2;3)

## **HTTP Method**

DELETE

## Attributes

Attribute	Туре	Description
multiStatusJsonList	<pre>[</pre>	Status: the http response code for this specific ID Description: the description Id: the ID of the object for this specific response

- 200 OK if no error occurred
- 409 Conflict
- 500 Internal Error

Developer's Guide 5. Security Rest API

# 5 Security Rest API

This chapter describes the REST API resources for the ARM security. The following APIs are described:

- Azure AD for REST Requests Authentication
- Get API
- Security Create API
- Security Update API
- Security Delete API
- Login API
- Azure AD for REST Requests Authentication

## 5.1 Get API

The  $\ARM_Configurator_IP>/ARM/v1/security/<ARM_attribute> when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve security attributes.$ 

#### **REST Resource**

```
<ARM_Configurator_IP>/ARM/v1/security/<ARM_attribute>
<ARM Configurator IP>/ARM/v1/security/<ARM attribute>/{id}
```

#### Where:

- <ARM\_attribute> requests all of the ids of the specified attribute (listed in the table below).
- [id] requests a specific ID of a specific attribute (listed in the table below

## **HTTP Method**

GET

### **Supported Content-Type**

application/json

#### **Attributes**

The ARM Configurator must respond to the GET request with JSON data that includes the request URI attribute. If the ID is not specified in the GET request, URI JSON data MUST contain an array of all specified elements defined in the database for the attribute.

Attribute	Туре	Description
operator	ARRAY OF: [     id: integer,     userName: string,     role: OperatorRoleType     url: string }	OperatorRoleType:  1 = ADMIN  2 = SECURITY_ADMIN  3 = DEVICE  4 = ROUTER  url – element REST path



Attribute	Туре	Description
	]	
credential	ARRAY OF: [ {     Id: Integer,     username: String     type: ENUM,     description: String }	Type:  1 = ADMIN  2 = SECURITY_ADMIN  3 = DEVICE  4 = ROUTER  5 = MONITOR  100 = NONE

## **HTTP Response**

- 200 OK
- 409 Conflict
- 500 Internal Error

## **5.1.1** Filter

There is a possibility to use a filter for specific requests. Filter should be added to the suffix of the URL, for example:

<ARM\_Configurator\_IP>/ARM/v1/security/<ARM\_element\_path>?filter=(r
oles=ENUM)

Filter	Available for these Requests	Description
roles	Operator	Filter Operators according to the role
type	Credentials	Filter credentials according to the type

Developer's Guide 5. Security Rest API

# 5.2 Security Create API

This section describes the Security Create API.

# **5.2.1** Create Operator

The <code><ARM\_Configurator\_IP>/ARM/v1/security/operator</code> URL when used with the POST method, provides the ability for the ARM Manager to send a request to the ARM Configurator to create an operator.

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/security/operator
<ARM Configurator IP>/ARM/v1/security/credentials

### **HTTP Method**

POST

## **Supported Content-Type**

application/json

#### **Attributes**

The request MUST contain JSON data that consists of the following attributes:

Attribute	Туре	Description
userName	STRING	The requested user name
password	STRING	The password
role	role: string	Role:  1 = admin 2 = security_admin The security level of the requested user  security_admin - Security administrator - can add/delete/modify users, and do all the rest  admin - Administrator - can NOT add/delete/modify users; but can do all the rest
description	String	Optional, only relevant for credentials creation

- 200 OK
- 201 Created (successful user creation)
- 403 Forbidden (incorrect credentials or with role of the user that does not match the security administrator)



# 5.3 Security Update API

This section describes the Security Update API.

## **5.3.1 Update Operator**

The  $\ARM_Configurator_IP>/ARM/v1/security/operator/{id} URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to update an operator.$ 

### **REST Resource**

```
<ARM_Configurator_IP>/ARM/v1/security/operator/{id}
<ARM_Configurator_IP>/ARM/v1/credentials/operator/{id}
```

Where {id} is the ID of the element in the database.

#### **HTTP Method**

PUT

### **Supported Content-Type**

application/json

### **Attributes**

Attribute	Туре	Description
userName	String	The requested user name
password	String	The user password.
role	role: string	Role:  1 = admin 2 = security_admin  The security level of the requested user:  ROLE_ SECURITY_ADMIN- Security administrator – can add/delete/modify users, and do all the rest  ROLE_ ADMIN - Administrator – can NOT add/delete/modify users; but can do all the rest.
description	String	Optional, Only relevant for credentials creation

- 200 OK
- 201 Created (successful user creation)
- 403 Forbidden (incorrect credentials or with role of the user that does not match the security administrator)

Developer's Guide 5. Security Rest API

# 5.4 Security Delete API

This section describes the Security Delete API.

# 5.4.1 Delete Operator API

The <arm\_Configurator\_IP>/ARM/v1/security/operator/{id} URL provides the ability for the ARM Manager to send a request to the ARM Configurator to delete an operator.

## **REST Resource**

```
<ARM_Configurator_IP>/ARM/v1/security/operator/{id}
<ARM_Configurator_IP>/ARM/v1/security/credentials/{id}
```

Where {id} is the ID of the element in the database.

### **HTTP Method**

DELETE

## **HTTP Response**

200 OK



# 5.5 Login API

The <ARM\_Configurator\_IP>/ARM/v1/login URL when used with the POST method, provides the ability for the ARM Manager to send a request to login.to the ARM Configurator.

#### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/login

## **HTTP Method**

POST

### **Supported Content-Type**

application/json

#### **Attributes**

The request MUST contain JSON data that consists of the following elements:

Attribute	Туре	Description
userName	STRING	The requested user name
password	STRING	The login password

### **HTTP Response**

- 200 OK- Response will be sent if the user was successfully authenticated.
- 401 Unauthorized in case of incorrect credentials or if the role of the user didn't match the correct privileges (security admin/admin).

## **Response Attributes**

The response provided by the ARM Configurator must contain JSON data with the following attributes:

Attribute	Туре	Description
userName	String	The requested user name (only in case of a successful login).
role	String	The role (permission) of the user (only in case of successful login).  For the role the following enum is used:  • SECURITY_ADMIN  • ADMIN
sessionTimeout	Integer	Session timeout in hours (only in case of a successful login).
inactivityPeriod	Integer	Inactive period in minutes (only in case of successful login).
description	String	Description for a successful login and for failed login.

Developer's Guide 5. Security Rest API

# 5.6 Azure AD for REST Requests Authentication

The <code><ARM\_Configurator\_IP>/ARM/v1/security/authentication/token URL</code> when used with the POST method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve an updated list of servers.

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/login/microsoft/authentication/token

### **HTTP Method**

POST

#### **Attributes**

The request MUST contain JSON data that consists of the following elements:

Attribute	Туре	Description
accessToken	String	The access token received from Microsoft
authenticationType	ENUM	ACCESS_TOKEN

### **HTTP Response**

- 200 OK- Response will be sent if the user was successfully authenticated.
- 401 Unauthorized in case of incorrect credentials or if the role of the user didn't match the correct privileges (security admin/admin).

Besides the response code the following Response object will be returned:

Attribute	Туре	Description
userName	String	The requested user name, only in case of successful login
role	String	The role (permission) of the user, only in case of successful login For the role the following enum is used: SECURITY_ADMIN ADMIN
roleName	String	
sessionTimeout	Integer	Session time out in hours, only in case of successful login
inactivityPeriod	Integer	Inactive period in minutes, only in case of successful login
description	String	Description in both cases
passwork	String	
token	String	Used the received token in the authorization header for any rest request to ARM



# 5.6.1 Revoking Azure User Tokens

Revoke all tokens created for Azure AD users:

The

<arm\_Configurator\_IP>/ARM/v1/security/authentication/token/revoke URL when used with the DELETE method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve an updated list of servers.

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/security/authentication/token/revoke

### **HTTP Method**

DELETE

Developer's Guide 6. Server Rest API

# 6 Server Rest API

This chapter describes the REST API resources for the ARM server. The following APIs are described:

- Get API
- Servers Create API
- Server Update API
- Server Delete API

## 6.1 Get API

The <arm\_Configurator\_IP>/ARM/v1/server URL when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve an updated list of servers.

### **REST Resource**

```
<ARM_Configurator_IP>/ARM/v1/server
<ARM_Configurator_IP>/ARM/v1/server/{id}
```

Where {id} requests a specific ID of a specific attribute (listed in the table below).

#### **HTTP Method**

GET

## **Supported Content-Type**

application/json

### **Attributes**

The ARM Configurator must respond to the GET request with JSON data that includes the request URI attribute. If the ID is not specified in the GET request, URI JSON data MUST contain an array of all specified elements defined in the database for the attribute.

Attribute	Туре	Description
Server	ARRAY OF: [      Id: integer     address: String     name: string,     type: string,     protocol: string,     port: integer,     url: string     state:ServerState     confRouterPort:Integer     adminState:Integer     memory:Integer	Protocol:  1 = http 2 = https  type:  ROUTING  url - element REST path  confRouterPort - conf <-> router  ServerState:  0 = AVAILABLE  1 = UNAVAILABLE  2 = INITIALIZING  3 = NOT_SYNC



Attribute	Туре	Description
	nodes:[	adminState:
	Integer	0 = UNLOCKED
	1	1 = LOCKED
	}	
	1	Nodes – the ids of the nodes for which the router is configured.

- 200 OK
- 409 Conflict
- 500 Internal error

Developer's Guide 6. Server Rest API

# 6.2 Servers Create API

This section describes the Servers Create API.

## 6.2.1 Create Server

The <ARM\_Configurator\_IP>/ARM/v1/server URL when used with the POST method, provides the ability for the ARM Manager to send a request to the ARM Configurator to create a new ARM Routing server.

## **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/server

## **HTTP Method**

POST

## **Supported Content-Type**

application/json

### Attributes

Attribute	Туре	Description
name	String	The name of the server
address	String	The IP address of the server
type	String	type: ROUTING
protocol	String	The protocol that is used by the server.
port	Integer	The port that is used by the server.
confRouterPort	Integer	The port that is used by the Configurator to communicate with the routers.
nodes	ARRAY OF: [ Integer ]	Ids of the router nodes.

- 201 Created
- 409 Conflict
- 500 Internal error



# 6.3 Server Update API

This section describes the Server Update API.

# 6.3.1 Update Server

The  $\ARM_Configurator_IP>/ARM/v1/server/{id}$  URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to update a server configuration.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/server/{id}

Where {id} is the ID of the element in the database.

## **HTTP Method**

PUT

## **Supported Content-Type**

application/json

### **Attributes**

Attribute	Туре	Description
address	String	IP address of the server.
protocol	String	The protocol that is used by the server.
port	Integer	The port that is used by the server.
confRouterPort	Integer	The port that is used by the by the configurator to communicate with the routers.

- 200 OK
- 409 Conflict
- 500 Internal error

Developer's Guide 6. Server Rest API

# 6.4 Server Delete API

This section describes the Server Delete API.

## 6.4.1 Delete Server API

The  $\ARM_Configurator_IP>/ARM/v1/server/{id}URL$  when used with the DELETE method, provides the ability for the ARM Manager to send a request to the ARM Configurator to delete a specific server.

## **REST Resource**

<ARM Configurator IP>/ARM/v1/server/{id}

Where {id} is the ID of the element in the database.

## **Supported Content-Type**

application/json

## HTTP Method

DELETE

## **HTTP Response**

200 OK



# 6.5 Servers Group API

# 6.5.1 Get All Server Groups

The <code><ARM\_Configurator\_IP>/ARM/v1/server/{id}URL</code> when used with the GET method, provides the ability for the ARM Manager to request to the ARM Configurator to retrieve a list of all server groups.

#### **REST Resource**

GET <ARM\_Configurator\_IP>/ARM/v1/server/group

## **Supported Content-Type**

application/json

### **HTTP Method**

GET

## **HTTP Response**

- 200 OK
- 409 Conflict
- 500 Internal error

### **Attributes**

Attribute	Туре	Description
id	Integer	Server Group ID
name	String	Server Group Name
policyBetweenGroups	ENUM	STICKY_PRIMARY, STICKY_LAST_AVAILABLE
policyInsideGroup	ENUM	ROUND_ROBIN, STICKY_PRIMARY, STICKY_LAST_AVAILABLE
groups	[ {   id: Integer   servers:{   id: Integer   priority: Integer }	The outer ID is the group ID The ID in the servers objects is the server ID from the database Priority is between 1 - 10

Developer's Guide 6. Server Rest API

# 6.5.2 Get Specific Server Group

The  $\ARM_Configurator_IP>/ARM/v1/server/{id}URL$  when used with the GET method, provides the ability for the ARM Manager to request to the ARM Configurator to retrieve a specific server group.

## **REST Resource**

GET <ARM Configurator\_IP>/ARM/v1/server/group/{id}

## **Supported Content-Type**

application/json

## HTTP Method

GET

## **HTTP Response**

- 200 OK
- 409 Conflict
- 500 Internal error

## **Attributes**

Attribute	Туре	Description
id	Integer	Server Group ID
name	String	Server Group Name
policyBetweenGroups	ENUM	STICKY_PRIMARY, STICKY_LAST_AVAILABLE
policyInsideGroup	ENUM	ROUND_ROBIN, STICKY_PRIMARY, STICKY_LAST_AVAILABLE
groups	[ {   id: Integer   servers:{   id: Integer   priority: Integer }	The outer ID is the group ID The ID in the servers objects is the server ID from the database Priority is between 1 - 10



## 6.5.3 Create Server Group API

The <ARM\_Configurator\_IP>/ARM/v1/server/group URL when used with the POST method, provides the ability for the ARM Manager to request to the ARM Configurator to create a specific server group.

## **REST Resource**

<ARM Configurator\_IP>/ARM/v1/server/group

## **Supported Content-Type**

application/json

### **HTTP Method**

POST

## **HTTP Response**

- 201 Created
- 409 Conflict
- 500 Internal error

#### **Attribute**

Attribute	Туре	Description
id	Integer	Server Group ID
name	String	Server Group Name
policyBetweenGroups	ENUM	STICKY_PRIMARY, STICKY_LAST_AVAILABLE
policyInsideGroup	ENUM	ROUND_ROBIN, STICKY_PRIMARY, STICKY_LAST_AVAILABLE
groups	[ {   id: Integer   servers:{   id: Integer   priority: Integer }	The outer ID is the group ID The ID in the servers objects is the server ID from the database Priority is between 1 - 10

Developer's Guide 6. Server Rest API

# 6.5.4 Update Server Group API

The  $\ARM_Configurator_IP>/ARM/v1/server/group$  URL when used with the PUT method, provides the ability for the ARM Manager to request to the ARM Configurator to update a specific server group.

## **REST Resource**

<ARM Configurator IP>/ARM/v1/server/group/{id}

## **HTTP Method**

PUT

## **Attributes**

Attribute	Туре	Description
id	Integer	Server Group ID
name	String	Server Group Name
policyBetweenGroups	ENUM	STICKY_PRIMARY, STICKY_LAST_AVAILABLE
policyInsideGroup	ENUM	ROUND_ROBIN, STICKY_PRIMARY, STICKY_LAST_AVAILABLE
groups	[	The outer ID is the group ID The ID in the servers objects is the server ID from the database Priority is between 1 - 10

- 200 OK
- 409 Conflict
- 500 Internal error



## 6.5.5 Delete Server Group API

The  $\ARM_Configurator_IP>/ARM/v1/server/group$  URL when used with the DELETE method, provides the ability for the ARM Manager to request to the ARM Configurator to delete a specific server group.

## **REST Resource**

<ARM Configurator IP>/ARM/v1/server/group/{id}

### **HTTP Method**

DELETE

## **Supported Content-Type**

application/json

- 200 OK
- 409 Conflict
- 500 Internal error

Developer's Guide 7. Action Status API

# 7 Action Status API

The <code><ARM\_Configurator\_IP>/ARM/v1/action/status/{id}</code> URL when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to determine the status of an unsynchronized action.

## **REST Resource**

<ARM Configurator IP>/ARM/v1/action/status/{id}

Where {id} is the unique identifier of the unsynchronized action.

#### **HTTP Method**

GET

## **Supported Content-Type**

application/json

- 202 Accepted in case the action is still in progress.
- 200 OK in case the action has been completed.



This page is intentionally left blank.

Developer's Guide 8. Network Planner API

# 8 Network Planner API

This chapter describes the REST API resources for the Network Planner. The following APIs are described:

- Get API
- Network Planner Create API
- Network Planner Update API
- Network Planner Delete API
- Network Planner Actions API

## 8.1 Get API

The <arm\_Configurator\_IP>/arm/v1/planning/<arm\_element\_path> URL when used with the GET method, provides the ability for the ARM Manager to request to the ARM Configurator to retrieve an ARM element.

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/planning/<ARM\_element\_path>
<ARM Configurator IP>/ARM/v1/planning/<ARM element path>/{id}

{id} - ID of the requested element

ARM Configurator must respond to the Get request with 200 respond and includes JSON data that depended from specified in request URI element and its ID. If the ID was not specified in get request URI JSON data must contain array of all specified elements defined in Topology data base.

#### **HTTP Method**

GET

### **Supported Content-Type**

application/json

### **Attributes**

The following attributes MUST be included:



Attribute	Туре	Description
map	{     nodes:     {         "id": {node}     }     "routingInterfaces": {         "id":{routing interface}     }     voipPeers:{         "id":{voipPeer}     }         "peerConnections": {         "id":{peer connection}     }         "internalPeerConnections": {         "id":{peer connection}     }         "connections":{         "id":{connection}     }     hashCode: Integer }	each object is a map of elements hashCode: the hash code of the full map object

Attribute	Туре	Description
node	ARRAY OF: [ {     adminState: String     deviceTypel: Integer	id- Node ID in the database operState -  1 = available 2 = not_available 3 = predeleted 4 = not_synced
	deviceTypeS: String id: Integer ipAddr: String isIpProfileAvailable: Boolean isOffline: Boolean name: String operState: String password: String prevSerialNum: String productType: String serialNum: String	adminState –  0 = unlock 1 = lock name- Name configured by ARM operator
	softwareVersion: String transportType: String useGeneralCredentials: Boolean username: String x: Interger y: Interger }	



Attribute	Туре	Description
,	Id: integer nodeld: integer nodeName: string name: string  voipPeerId: integer operState: ENUM adminState: ENUM peerConnectionNodeType: ring(enum) nativeName: String tgrp: String destNormalizationGroupId: integer srcNormalizationGroupId: integer isInternal:Boolean isProxySetWithIp:Boolean rild: Integer weight: Integer ipGroupType: String(enum) topologyGroups: [integer] result: String(enum) quality: integer isOffline: Boolean callsQuotald: integer callsQuotaName: String callsDuration: Double quotaState: String(enum) quotaWarningReached: Boolean quotaLimitReached: Boolean cacProfileId: integer cacState: String(enum) cacProfileName: String	operState –  1 = available 2 = not_available 3 = predeleted 4 = temp_not_available 5 = not_synced  adminState –  0 = unlock 1 = lock url – element REST path peerConnectionNodeType –  0 = IPGroup 1 = TrunkGroup 2 = Virtual ipGroupType—  0 = Server 1 = User 2 = Gatway quotaState –  0 = UNBLOCK 1 = BLOCK_OUTGOING cacState—  0 = UNBLOCK 1 = BLOCK 2 = BLOCK_INCOMING 3 = BLOCK_OUTGOING result the result of the quality calculation - enum BAD, FAIR, GOOD or UNKNOWN

Attribute	Туре	Description
voippeer	ARRAY OF:  [      Id: integer     name: string,     deviceType: string,     url: string     isOffline: Boolean  }	deviceType – 0 = NA 1 = PSTN 2 = SIP_Trunk 3 = PBX 4 = IP_PBX 5 = IP_Phones url – element REST path
connection	ARRAY OF:  [      id: integer     weight: integer     name: string,     URI: string,     adminState: string     isOffline: Boolean     connections:  [      {          offline: Boolean         srcNodeld: integer         destNodeld: integer         srcRoutingInterface: integer         destRoutingInterface: integer         operState: string     }      ]      result: String(enum) }	By default each connection is two-way  Each direction has status  Direction 1 –from Node1 to Node2  Direction2- from Node2 to Node1  weight [1-100]  Default =50  operState:  1 = available 2 = not_available 3 = predeleted 4 = temp_not_available 5 = not_synced  adminState: 0 = unlock 1 = lock  url – element REST path  result the result of the quality calculation - enum BAD, FAIR, GOOD or UNKNOWN  this will be send for both the of the edges and the connection itself



Attribute	Туре	Description
routingInterface	ARRAY OF:  [	operState:  1 = available 2 = not_available 3 = predeleted 4 = temp_not_available 5 = not_synced  transportType:  UDP TCP TLS  url – element REST path

# **8.1.1** Filter

There is a possibility to use a filter for specific requests. The filter should be added to the suffix of the URL, for example:

# **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/planning/peerCon?filter=(nodeId=100)

#### **HTTP Method**

GET

# **Supported Content-Type**

application/json

# Attributes

The following attributes MUST be included:

Filter	Available for these Requests	Description
isOffline	node peerCon voippeer connection	Filter results for elements that are only offline and that weren't imported in.
name	node peerCon voippeer connection	Contains for partial search Equals for regular search

- 200 OK
- 500 Internal error
- 409 Conflict



# 8.2 Network Planner Create API

# 8.2.1 Create Connection

The <code><ARM\_Configurator\_IP>/ARM/v1/planning/connection</code> URL when used with the POST method, provides the ability for the ARM Manager to request to the ARM Configurator to create a network planner.

#### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/planning/connection

# **HTTP Method**

POST

# **Supported Content-Type**

application/json

#### **Attributes**

The following attributes MUST be included:

Attribute	Туре	Description
name	String	Unique name of the network planner.
weight	integer	Weight of the network planner
connections	Array of 2 entries, 1 for each direction  [	

- 201 Created
- 500 Internal error
- 409 Conflict

# 8.2.2 Create PeerConnection

The <code><ARM\_Configurator\_IP>/ARM/v1/planning/peerCon</code> URL when used with the POST method, provides the ability for the ARM Manager to request to the ARM Configurator to create a peer connection.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/planning/peerCon

# **HTTP Method**

POST

# **Supported Content-Type**

application/json

# Attributes

It MUST contain the following arguments:

Attribute	Туре	Description
name	String	The name of the peer connection.
nodeld	Integer	The node ID of the peer connection.
peerConnectionNodeType	PeerConnectionNodeType	IPGroup or TrunkGroup
voipPeerId	Integer	If null, ARM will create the voip peer
rild	Integer	If null ARM will pick the SBC dummy routing interface
weight	Integer	The weight assigned to the peer connection.

- 201 Created
- 500 Internal error
- 409 Conflict



# 8.2.3 Add Node to ARM

The  $\ARM_Configurator_IP>/ARM/v1/planning/node URL$  when used with the POST method, provides the ability for the ARM Manager to request to the ARM Configurator to create a planning node.

#### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/planning/node

#### **HTTP Method**

POST

# **Supported Content-Type**

application/json

#### **Attributes**

It MUST contain the following arguments:

Attribute	Туре	Description
ipAddr	String	The IP address of the node
userName	String	Optional – otherwise Admin
password	String	Optional – otherwise Admin
productType	String	One of the following: SBC GW HYBRID
х	Integer	X coordinate value
У	Integer	Y coordinate value

- 201 Created
- 500 Internal error
- 409 Conflict

# 8.2.4 Add VoIP Peer to ARM

The <ARM\_Configurator\_IP>/ARM/v1/planning/voippeer URL when used with the POST method, provides the ability for the ARM Manager to request to the ARM Configurator to create a VoIP peer.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/planning/voippeer

# **HTTP Method**

POST

# **Supported Content-Type**

application/json

#### Attributes

It MUST contain the following arguments:

Attribute	Туре	Description
deviceType	String	IP_PHONES, IP_PBX, PSTN, NA, PBX, SIP_TRUNK
name	String	Name of the VP
х	Integer	Value of the x coordinate
у	Integer	Value of the y coordinate

- 201 Created
- 500 Internal error
- 409 Conflict



# 8.3 Network Planner Update API

At the suffix of each URL for update API there is a {id} sign which represents the ID of the element in the database.

# 8.3.1 Update Connection

The  $\ARM_Configurator_IP>/ARM/v1/planning/connection/{id} URL when used with the PUT method, provides the ability for the ARM Manager to request to the ARM Configurator to update a specific VoIP connection.$ 

#### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/planning/connection/{id}

#### **HTTP Method**

PUT

# **Supported Content-Type**

application/json

#### **Attributes**

It MUST contain the following arguments:

Attribute	Туре	Description
name	string	The connection name.
weight	integer	The weight assigned to the connection.  1-100  Default - 50
result	String	BAD, FAIR, GOOD, UNKNOWN

- 200 OK
- 500 Internal error
- 409 Conflict

# 8.3.2 Update VOIP Peer

The <code><ARM\_Configurator\_IP>/ARM/v1/planning/voippeer/{id}</code> URL when used with the PUT method, provides the ability for the ARM Manager to request to the ARM Configurator to update a VOIP Peer.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/planning/voippeer/{id}

# **HTTP Method**

PUT

# **Supported Content-Type**

application/json

#### Attributes

It MUST contain the following arguments:

Attribute	Туре	Description
deviceType	string	0 = NA 1 = PSTN 2 = SIP_trunk 3 = PBX 4 = IP_PBX 5 = IP_PHONES
Name	string	Name of the VOIP Peer

- 200 OK
- 500 Internal error
- 409 Conflict



# 8.3.3 Update VoIP Peers Map Locations

The <code><ARM\_Configurator\_IP>/ARM/v1/planning/voippeer/location URL</code> when used with the PUT method, provides the ability for the ARM Manager to request to the ARM Configurator to save the location of the VoIP peers elements.

#### **REST Resource**

PUT <ARM Configurator IP>/ARM/v1/planning/voippeer/location

# **HTTP Method**

PUT

# **Supported Content-Type**

application/json

#### **Attributes**

It MUST contain the following arguments:

Attribute	Туре	Description
id	Integer	ID of the VoIP Peers Map locations.
х	Integer	X coordinate value.
у	Integer	Y coordinate value.

- 200 OK
- 500 Internal error
- 409 Conflict

# 8.3.4 Update Peer Connection

The <code><ARM\_Configurator\_IP>/ARM/v1/planning/peerCon/{id}</code> URL when used with the PUT method, provides the ability for the ARM Manager to request to the ARM Configurator to update a peer connection.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/planning/peerCon/{id}

# **HTTP Method**

PUT

# **Supported Content-Type**

application/json

#### **Attributes**

The request MUST contain the following data elements::

Attribute	Туре	Description
name	string	Name of the Peer connection.
voipPeerId	Integer	ID of the Peer connection.
result	String	BAD, FAIR, GOOD, UNKNOWN

- 200 OK
- 500 Internal error
- 409 Conflict



# 8.3.5 Update Node

The  $\ARM_Configurator_IP>/ARM/v1/planning/node/{id}$  URL when used with the PUT method provides the ability for the ARM Manager to request to the ARM Configurator to update a specific node.

#### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/planning/node/{id}

# **HTTP Method**

PUT

# **Supported Content-Type**

application/json

#### **Attributes**

The request MUST contain the following data elements:

Attribute	Туре	Description
name	string	=
transportType	string	Either HTTP or HTTPS
useGeneralCredentials	Boolean	Either node should use general credentials
userName	String	userName for connecting to Node
password	String	-
ipAddress	String	-

- 200 OK
- 500 Internal error
- 409 Conflict

# 8.3.6 Update Nodes Map Locations

The <code><ARM\_Configurator\_IP>/ARM/v1/planning/node/location</code> URL when used with the PUT method provides the ability for the ARM Manager to request to the ARM Configurator.to save the location of the node elements.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/planning/node/location

# **HTTP Method**

PUT

# **Supported Content-Type**

application/json

#### **Attributes**

The request MUST contain the following data elements:

Attribute	Туре	Description
id	Integer	ID of the node location
х	Integer	X coordinate
у	Integer	Y coordinate

- 200 OK
- 500 Internal error
- 409 Conflict



# 8.4 Network Planner Delete API

When ARM Manager sends a Delete request to ARM Configurator, it includes a suffix of each URL for update API (id) sign which represents the ID of the element in the database.

#### REST Resource

```
<ARM_Configurator_IP>/ARM/v1/planning/peerCon/{id}
<ARM_Configurator_IP>/ARM/v1/planning/connection/{id}
<ARM_Configurator_IP>/ARM/v1/planning/voippeer/{id}
<ARM_Configurator_IP>/ARM/v1/planning/node/{id}
<ARM_Configurator_IP>/ARM/v1/planning/map
```

#### **HTTP Method**

DELETE

# **Supported Content-Type**

application/json

**Note:** The delete operation is only available for elements which are not part of a routing rules, or policy studio. Clearing the map will delete all the offline elements from the database and remove the imported elements.

- 200 OK
- 500 Internal error
- 409 Conflict

# 8.5 Network Planner Actions API

# 8.5.1 Import Full Topology

The <arm\_Configurator\_IP>/ARM/v1/planning/import URL when used with the POST method provides the ability for the ARM Manager to request to the ARM Configurator.to import all the elements from the regular map view into the offline planner.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/planning/import

# **HTTP Method**

POST

#### **Supported Content-Type**

application/json

#### **HTTP Response**

- 200 OK.
- 409 in case a previous sync all nodes action is in progress on the server. The server will not start a new action if a previous one is in progress.

# 8.5.2 Import Nodes

The <code><ARM\_Configurator\_IP>/ARM/v1/planning/node/{id}/import URL</code> when used with the POST method provides the ability for the ARM Manager to request to the ARM Configurator.to import specific nodes from the regular map view into the offline planner.

#### **REST Resource**

POST <ARM\_Configurator\_IP>/ARM/v1/planning/node/{id}/import POST <ARM\_Configurator\_IP>/ARM/v1/planning/node/import

{id} - database ID of the node

# **HTTP Method**

POST

#### **Supported Content-Type**

application/json

- 201 Created
- 500 Internal error
- 409 Conflict



# 8.5.3 Export Node

The  $\ARM_Configurator_IP>/ARM/v1/planning/node/{id}/export$  URL when used with the POST method provides the ability for the ARM Manager to request to the ARM Configurator to export specific nodes from the offline planner.

#### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/planning/node/{id}/export

{id} - database ID of the node

#### **HTTP Method**

POST

# **Supported Content-Type**

application/json

- 202 Accepted
- 500 Internal error
- 409 Conflict.

# 8.5.4 Lock Node Action

The  $\ARM_Configurator_IP>/ARM/v1/planning/node/{id}/lock URL when used with the POST method provides the ability for the ARM Manager to request to the ARM Configurator to lock a node.$ 

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/planning/node/{id}/lock

{id} - database ID of the node

# HTTP Method

POST

#### **Supported Content-Type**

application/json

**Note:** For multiple lock operation Multi response JSON is returned with the appropriate HTTP response code for each element.

#### **Attributes**

The request MUST contain the Lock node request API MUST contain JSON data of the following argument:

Attribute	Туре	Description
lock	string	1 = lock 0 = unlock

- 201 Created
- 500 Internal error
- 409 Conflict



# 8.5.5 Lock Peer Connection Action

The <code><ARM\_Configurator\_IP>/ARM/v1/planning/node/{id}/lock URL</code> when used with the POST method provides the ability for the ARM Manager to request to the ARM Configurator to lock a specific peer connection.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/planning/peerCon/{id}/lock

{id} - database ID of the peer connection

#### **HTTP Method**

POST

# **Supported Content-Type**

application/json

**Note:** For multiple lock operation Multi response JSON is returned with the appropriate HTTP response code for each element.

#### **Attributes**

Lock node request API MUST contain JSON data of the following argument:

Attribute	Туре	Description
lock	string	1=lock
		0=unlock

- 201 Created
- 500 Internal error
- 409 Conflict

# 9 Identity

This chapter describes the REST API resources for the LDAP server. The following APIs are described:

- Get API
- Identity Create API
- Identity Update API
- Identity Delete API

# 9.1 Get API

The <code>ARM\_Configurator\_IP>/ARM/v1/identity/<ARM\_attribute> URL</code> when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve specific LDAP attributes for server, userGroup, users and user group.

#### **REST Resource**

```
<ARM_Configurator_IP>/ARM/v1/identity/<ARM_attribute>
<ARM Configurator IP>/ARM/v1/identity/<ARM attribute>/{id}
```

#### Where:

- <ARM\_attribute> requests all of the ids of the specified attribute (listed in the table below).
- [id] requests a specific ID of a specific attribute (listed in the table below).

#### **HTTP Method**

GET

#### **Supported Content-Type**

application/json

#### **Attributes**

The ARM Configurator must respond to the Get request with JSON data that includes the request URI attribute. If the ID is not specified in the GET request, URI JSON data MUST contain an array of all specified elements defined in the database for the attribute.

The following attributes MUST be included:

Attribute	Туре	Description
server	[     id: Integer     name: String     status: serverStatus     host: String     port: Integer     dn: String     searchFilter: String	serverStatus:  0 = AVAILABLE  1 = UNAVAILABLE  syncIntervalMinutes (in minutes)



Attribute	Туре	Description
	baseObject: String numOfUsers: Integer sslEnabled: boolean certificate: String timeout: Integer syncIntervalMinutes: Integer LastSyncTimestamp: String fullSyncHour: Integer fullSyncMinute: Integer fullSyncIntervalInDays: Integer lastFullSyncTimestamp: String dicAttrMapping:  [	LastSyncTimeStamp and lastFullSyncTimestamp - UTC formatted string: "yyyy-mm-ddThh:mm:ss.mmmZ"
userGroup	[     id: Integer     name: String     associatedDialable: String     conditions:     [         dicAttrName: String         operator: LogicalOperatorEnum         values:         [             String         ]      }     ] }	LogicalOperatorEnum:  0 = EQUALS  1 = NOT_EQUALS  2 = CONTAINS  3 = NOT_CONTAINS  associatedDialable: name of dialable attribute
user	{     Id: long     name: String     origin: String     groups:	origin: "LOCAL" in case of local user or name of the AD in case of AD user dicAttributes are dynamic, according to the dictionary in the system

Attribute	Туре	Description
	[ groupId: String ], dicAttributes:  [ { local: boolean dicAttrId: Integer value: String } ]	
user/count	Integer	Total number of users
user/export	CSV file	Export Users data to CSV file
users	{   cursor:   {   before: Integer   },   users:   [     {     Id: long     name: String     origin: String     groups:      [         groupId: String     ],     dicAttributes:      [         {         local: boolean             dicAttrId: Integer         value: String       }     ]   }   ] }	origin: "LOCAL" in case of local user or name of the AD in case of AD user. dicAttributes are dynamic, according to the dictionary in the system  cursor: before: Returns the index of the previous page (where 0 represents page 1). after: Returns the index of the next page (where 0 represents page 1).
dicAttribute	[ { Id: Integer	defaultRemoteName: Remote Attribute to map dicAttribute to by default



Attribute	Туре	Description
	name: String description: String primary: boolean defaultRemoteName: String local: boolean dialable: boolean }	local: is attribute created to be "local" or already to be mapped to AD defaultRemoteName: To display this option in the Wel interface (not mapped internally)
illeRepository	[     Id: Integer     name: String     status: FileRepositoryStatus     delimiter: Character     isFileHasHeaders: Boolean     uniquePropertyId: Integer     isNameUnique: Boolean     nameFileMapping: String     nameFileLocation: Integer     numberOfUsers: Integer     lastTimestamp: String     description: String     dicAttrMapping: [         dicAttrId: Integer         dicAttrName: String         fileRepositoryAttrName: String         fileRepositoryAttrLocation: Integer         normalizationGroupId: Integer ]	FileRepositoryStatus:  0 = INITIALIZING  1 = ACTIVE  2 = ERROR

- 409 Conflict ID does not exist.
- 200 OK if at least one resource is found.
- 204 No Content Response.

# 9.1.1 Get Filter API

#### The

<ARM\_Configurator\_IP>/ARM/v1/identity/user?filter=(seachString~Alex
,origin=1;2)URL when used with the GET method provides the ability for the ARM
Manager to send a request to the ARM Configurator to filter specific requests. The filter
should be added to the suffix of the URL, for example:

#### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/identity/user?filter=(seachString~Ale
x,origin=1;2)

# **Supported Content-Type**

application/json

#### **HTTP Method**

GET

#### **Attributes**

Filter	Available for these Requests	Description
name	user	Filters only the user name column (Contains ~)
limit	user	Limits the number of result items that can be retrieved. For example, 100 items.
before	user	Specifies the page index for which to retrieve items.
after	user	Specifies the page index for which to retrieve items.
userGroup	user	Filters according to the user group ID (Equals =)
searchString	user	Filters according to any attribute of the user (Contains ~)
origin	user	Filters according to the LDAP server ID, -1 for local, can have multiple values (Equals =)
sort	user	Sorts the results according to the column name that was sent. If "-" was sent in the beginning, descending order will be used. For example &sort=name &sort=-Country Note: if "origin" is used, ARM will sort by the server ID and not in alphabetical order.

- 200 OK at least one resource is found.
- 204 No Content Response.



# 9.2 Identity Create API

This section describes the Identity Create API for creating an LDAP server for managing LDAP server users.

# 9.2.1 Server Create API

The <ARM\_Configurator\_IP>/ARM/v1/identity/server URL when used with the POST method sends a request to the ARM Configurator to create an LDAP server.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/identity/server

# **Supported Content-Type**

application/json

# HTTP Method

POST

# Attributes

Attribute	Туре	Description
name	String	A unique name for the LDAP server (if the name is not unique, 409 Conflict is returned).
password	String	The password of the LDAP server.
host	String	The name of the LDAP server host.
port	Integer	The LDAP server port.
dn	String	The Distinguished Nam of the LDAP server.
searchFilter	String	The LDAP search filter.
baseObject	String	The LDAP base object.
sslEnabled	boolean	Determines whether SSL is enabled for the connection with the LDAP server.
certificate	String	The certificate that secures the connection with the LDAP server.
syncIntervalMinutes	Integer	The interval time (in minutes) when partial synchronization is performed to retrieve users from the LDAP server. This operation retrieves users that have changed since the last partial sync was run.
fullSyncHour	Integer	The hour when full synchronization is performed to retrieve all users from the LDAP server.

Attribute	Туре	Description
fullSyncMinute	Integer	The minute in the hour when full synchronization is performed to retrieve all users from the LDAP server.
timeout	Integer	The timeout for connection with the LDAP server (in minutes).
fullSyncIntervalInDays	Integer	The interval time (in days) when full synchronization is performed to retrieve all users from the LDAP server.
dicAttrMapping	[	The dictionary attribute mapping with the LDAP server.

- 201 Created
- 409 Conflict
- 500 Internal Error



# 9.2.2 Server Test API

The  $\ARM_Configurator_IP>/ARM/v1/identity/server/test$  URL when used with the POST method, provides the ability for the ARM Manager to send a request to the ARM Configurator to test an LDAP server.

# **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/identity/server/test

# **HTTP Method**

POST

# **Supported Content-Type**

application/json

# **Request Attributes**

Attribute	Туре	Description
name	String	A unique name for the LDAP server (if the name is not unique, 409 Conflict is returned).
password	String	The password of the LDAP server.
host	String	The name of the LDAP server host.
port	Integer	The LDAP server port
dn	String	The Distinguished Nam of the LDAP server.
searchFilter	String	The LDAP search filter.
baseObject	String	The LDAP base object.
sslEnabled	boolean	Determines whether SSL is enabled for the connection with the LDAP server.
certificate	String	The certificate that secures the connection with the LDAP server.
syncIntervalMinutes	Integer	The interval time (in minutes) when partial synchronization is performed with the LDAP server. This operation retrieves users that have changed since the last partial sync was run.
fullSyncHour	Integer	The hour when full synchronization is performed to retrieve all users from the LDAP server.
fullSyncMinute	Integer	The minute in the hour upon when full synchronization is performed to retrieve all users from the LDAP server.
timeout	Integer	The timeout for connection with the LDAP server (in minutes).

Attribute	Туре	Description
fullSyncIntervalInDays	Integer	The interval time (in days) upon when full synchronization is performed to retrieve users from the LDAP server.
dicAttrMapping	[	The dictionary attribute mapping with the LDAP server.

# Response Attributes

The following attributes MUST be included in the response:

Attribute	Туре	Description
connectionStatus	String	Status of the connection with the LDAP server.
availableAttributes	[ {  availableAttribute: String } ]	Attributes available in this LDAP server that can be used as attribute mappings.

- 201 Created
- 409 Conflict



# 9.2.3 User Group Create API

The  $\ARM_Configurator_IP>/ARM/v1/identity/userGroup$  URL when used with the POST method, provides the ability for the ARM Manager to send a request to the ARM Configurator to create an LDAP User Group.

#### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/identity/userGroup

# **HTTP Method**

POST

# **Supported Content-Type**

application/json

# Attributes

Attribute	Туре	Description
name	String	The unique name of the LDAP server user group. If the name is not unique, 409 CONFLICT is returned.
associatedDialable	String	Dialable property associated with the user group. The User Group must have an associated dialable property, otherwise, a 409 CONFLICT is returned.
conditions	[     dicAttrName: String     operator: LogicalOperatorEnum     values:        [             String        ]     } ]	LogicalOperatorEnum:  0 = EQUALS  1 = NOTEQUALS  2 = CONTAINS  3 = NOT_CONTAINS

- 201 Created
- 409 Conflict
- 500 Internal Server Error

# 9.2.4 UserGroup Dry Run API

The <code><ARM\_Configurator\_IP>/ARM/v1/identity/userGroup/dryRun</code> URL when used with the POST method, provides the ability for the ARM Manager to send a request to the ARM Configurator to verify which LDAP users are suitable for a specific LDAP User Group before the User Group is generated.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/identity/userGroup/dryRun

#### **HTTP Method**

POST

# **Supported Content-Type**

application/json

#### Attributes

Attribute	Туре	Description
name	String	The Unique name of the user group. If the name is not unique, the 409 CONFLICT is returned.
associatedDialable	String	Dialable property associated with the user group. The User Group must have an associated dialable property, otherwise, a 409 CONFLICT is returned.
conditions	[     dicAttrName: String     operator: LogicalOperatorEnum     values:        [             String        ]     } ]	LogicalOperatorEnum:  0 = EQUALS  1 = NOTEQUALS  2 = CONTAINS  3 = NOT_CONTAINS

# **HTTP Response**

- 201 Created
- 409 Conflict
- 500 Internal Server Error

A filter should be added to the suffix of the URL, for example:



# Filter Example

GET

<ARM\_Configurator\_IP>/ARM/v1/identity/userGroup/dryRun?filter=(sea chString~A)

Filter	Available for these Requests	Description
searchString	user	Filters according to any attribute of the user (Contains ~).
limit	user	Limit the number of the results
before	user	Returns all the events prior to this ID (larger than this ID).
after	user	Returns all the events after this ID (smaller than this ID).
sort	user	Sorts the result.

# 9.2.5 User Create API

The <code><ARM\_Configurator\_IP>/ARM/v1/identity/user</code> URL when used with the POST method, provides the ability for the ARM Manager to send a request to the ARM Configurator to create an LDAP user.

#### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/identity/user

# **HTTP Method**

POST

# **Supported Content-Type**

application/json

# Attributes

Attribute	Туре	Description
name	String	A unique name for local users. If the name is not unique, 409 CONFLICT message is returned.
dicAttributes	[	Dynamic JSON constructed according to dicAttributes. If dicAttrld does not exist, 409 CONFLICT status is returned.

- 201 Created
- 409 Conflict
- 500 Internal Error



# 9.2.6 Dictionary Attribute Create API

The <code><ARM\_Configurator\_IP>/ARM/v1/identity/dicAttribute URL</code> when used with the POST method, provides the ability for the ARM Manager to send a request to the ARM Configurator to create a Property Dictionary (for mapping with the AD objects) in the UI.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/identity/dicAttribute

#### **HTTP Method**

POST

# **Supported Content-Type**

application/json

#### **Attributes**

Attribute	Туре	Description
dicAttribute	{     name: String     description: String     dialable: boolean     primary: boolean     defaultRemoteName: String }	The unique name of the dictionary attribute. If the name is not unique, 409 CONFLICT status is returned. defaultRemoteName: The default mapping of this property in the LDAP server.

- 201 Created
- 409 Conflict
- 500 Internal Error

# 9.2.7 File Repository Create API

The <code><ARM\_Configurator\_IP>/ARM/v1/identity/</code> fileRepository URL when used with the POST method, provides the ability for the ARM Manager to send a request to the ARM Configurator to create a File Repository (for mapping with the AD objects) in the ARM Web interface.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/identity/fileRepository

# **HTTP Method**

POST

# **Supported Content-Type**

application/json

#### **Attributes**

Attribute	Туре	Description
name	String	Indicates the unique name for file repositories. If the name is not unique, 409 CONFLICTED status is returned.
status	Integer	Indicates the status of the File Repository as indicated in the adjacent column.  FileRepositoryStatus:  0 = INITIALIZING  1 = ACTIVE  2 = ERROR
delimiter	Character	Indicates the character used to separate entries in the File repository.  This can be one of the following: ',', ';' or ' ').
isFileHasHeaders	boolean	Indicates whether the file contains headers in the first line.
uniquePropertyId	Integer	When the unique property of the user repository is a user dictionary attribute, indicates the ID of this unique attribute. If 'Name' is set as the unique attribute for the user repository, then this attribute is Null.
isNameUnique	boolean	If the unique property is set to "Name", this attribute is TRUE.  If the unique property is taken from the property dictionary, this attribute is FALSE.
nameFileMapping	String	File mapping for the "name" property.
nameFileLocation	Integer	Indicates the column location e.g. 3 indicates that the "Name" property is the third column in the file.



Attribute	Туре	Description
dicAttrMapping	[     dicAttrId: Integer     dicAttrName: String     fileRepositoryAttrName:     String  fileRepositoryAttrLocation:     Integer     normalizationGroupId:     Integer     } ]	Mapping of the dictionary attributes specified in the adjacent array.

Developer's Guide 9. Identity

# 9.3 Identity Update API

This section describes the Identity Update API.

# 9.3.1 Server Update API

The <code><ARM\_Configurator\_IP>/ARM/v1/identity/server/{id}</code> URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to update an LDAP server.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/identity/server/{id}

Where {id} is the element in the database.

### **HTTP Method**

PUT

# **Supported Content-Type**

application/json

Attribute	Туре	Description
name	String	A unique name for the LDAP server (if the name is not unique, 409 Conflict is returned).
password	String	The password of the LDAP server.
host	String	The name of the LDAP server host.
port	Integer	The LDAP server port
dn	String	The Distinguished Nam of the LDAP server.
searchFilter	String	The LDAP search filter.
baseObject	String	The LDAP base object
sslEnabled	boolean	Determines whether SSL is enabled for the connection with the LDAP server.
certificate	String	The certificate that secures the connection with the LDAP server.
syncIntervalMinutes	Integer	The interval time (in minutes) when partial



Attribute	Туре	Description
		synchronization is performed with the LDAP server. This operation retrieves users that have changed since the last partial sync was run.
fullSyncHour	Integer	The hour when full synchronization is performed to retrieve all users from the LDAP server.
fullSyncMinute	Integer	The minute in the hour when full synchronization is performed to retrieve all users from the LDAP server.
timeout	Integer	The timeout for connection with the LDAP server (in minutes).
fullSyncIntervalInDays	Integer	The interval time (in days) when full synchronization is performed to retrieve all users from the LDAP server.
dicAttrMapping	[	The dictionary attribute mapping with the LDAP server.

- 200 OK
- 409 Conflict status for non-existing ID

Developer's Guide 9. Identity

# 9.3.2 User Group Update API

The <code><ARM\_Configurator\_IP>/ARM/v1/identity/userGroup/{id}</code> URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to update an Indentity User Group.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/identity/userGroup/{id}

Where {id} is the element in the database.

### **HTTP Method**

PUT

# **Supported Content-Type**

application/json

### Attributes

Attribute	Туре	Description
name	String	The unique name of the LDAP user group. If the name is not unique, 409 CONFLICT is returned
associatedDialable	String	Dialable property associated with the user group. The User Group must have an associated dialable property, otherwise, a 409 CONFLICT is returned.
conditions	[     dicAttrName: String     operator: LogicalOperatorEnum     values:     [         value:String     ] }	LogicalOperatorEnum:  0 = EQUALS  1 = NOTEQUALS  2 = CONTAINS  3 = NOT_CONTAINS

- 200 OK
- 409 Conflict for non-existing ID.



# 9.3.3 User Update API

The <code><ARM\_Configurator\_IP>/ARM/v1/identity/user/{id}</code> URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to update an Identity user.

#### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/identity/user/{id}

Where {id} is the element in the database.

#### **HTTP Method**

PUT

# **Supported Content-Type**

application/json

#### **Attributes**

Attribute	Туре	Description
name	String	The unique name for local users. If the name is not unique, 409 CONFLICT is returned.
dicAttributes	[	Dynamic JSON constructed according to dictionary attributes.  Validation: it is not possible to define attributes for a remote user which are part of the mapping between the dictionary and the user's AD.  If this occurs, 409 CONFLICT is returned.

- 200 OK
- 409 Conflict for non-existing ID

Developer's Guide 9. Identity

# 9.3.4 Dictionary Attribute Update API

The <code><ARM\_Configurator\_IP>/ARM/v1/identity/dicAttribute/{id}</code> URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to update a Dictionary attribute.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/identity/dicAttribute/{id}

Where {id} is the element in the database.

### **HTTP Method**

PUT

# **Supported Content-Type**

application/json

### **Attributes**

Attribute	Туре	Description
name	String	The unique name for the dictionary attribute.
		If the name is not unique, 409 CONFLICT is returned.
description	String	The description of the dictionary attribute.
dialable	boolean	Indicates whether the LDAP AD property is 'dialable'.
primary	boolean	Indicates whether to display the 'primary' property in the user's screen.

- 200 OK
- 409 Conflict for non-existing ID



# 9.3.5 File Repository Update API

The <arm\_Configurator\_IP>/arm/v1/identity/fileRepository/{id} URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to update a specific File Repository attribute.

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/identity/ fileRepository/{id}

### **HTTP Method**

PUT

### **Supported Content-Type**

application/json

Attribute	Туре	Description
name	String	Indicates the unique name for the file repository. If not, 409 CONFLICTED status returned.
status	Integer	Indicates the status of the file repository as specified in the adjacent column.  FileRepositoryStatus:  0 = INITIALIZING  1 = ACTIVE  2 = ERROR
delimiter	Character	Indicates the character used to separate entries in the File repository.  This can be one of the following: ',', ';' or ' ').
isFileHasHeaders	boolean	Indicates whether the file contains headers in the first line.
uniquePropertyId	Integer	If the unique property is set to "Name", this attribute is TRUE.  If the unique property is taken from the property dictionary, this attribute is FALSE.
isNameUnique	boolean	If the unique property is set to "Name", this attribute is TRUE.  If the unique property is taken from the property dictionary, this attribute is FALSE.
nameFileMapping	String	File mapping for the "name" property.
nameFileLocation	Integer	Indicates the column location e.g. 3 indicates that the "Name" property is the third column in the file.
dicAttrMapping	[ {	Mapping of the dictionary attributes specified in the adjacent array

Developer's Guide 9. Identity

Attribute	Туре	Description
	dicAttrld: Integer dicAttrName: String fileRepositoryAttrName: String fileRepositoryAttrLocation: Integer normalizationGroupId: Integer } ]	



# 9.4 Identity Delete API

This section describes the Delete API.

### 9.4.1 Server Delete API

The <arm\_Configurator\_IP>/arm/v1/identity/server/{id} URL when used with the DELETE method, provides the ability for the ARM Manager to send a request to the ARM Configurator to delete an Identity server. When deleting the server, all its users' local attributes are also deleted.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/identity/server/{id}

Where {id} is the element in the database.

#### **HTTP Method**

DELETE

#### **HTTP Response**

409 Conflict for non-existing ID.

# 9.4.2 User Group Delete API

The  $\ARM_Configurator_IP>/ARM/v1/identity/userGroup/{id} URL when used with the DELETE method, provides the ability for the ARM Manager to send a request to the ARM Configurator to delete a User Group.$ 

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/identity/userGroup/{id}

Where {id} is the element in the database.

### HTTP Method

DELETE

#### **Supported Content-Type**

application/json

### **HTTP Response**

409 Conflict status when trying to delete a User Group with associated Routing Rules.

Developer's Guide 9. Identity

# 9.4.3 User Delete API

The <ARM\_Configurator\_IP>/ARM/v1/identity/user/{id} URL when used with the DELETE method, provides the ability for the ARM Manager to send a request to the ARM Configurator to delete a user.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/identity/user/{id}

Where {id} is the element in the database.

For multiple delete:

```
<ARM Configurator IP>/ARM/v1/identity/user?filter=(id=id1;id2;...)
```

The response will be a multi-response JSON with the appropriate response code for each request ID.

#### **HTTP Method**

DELETE

### **Supported Content-Type**

application/json

### **HTTP Response**

409 Conflict when trying to delete an AD user.

### **Attributes (Multi-delete)**

Attribute	Туре	Description
multiStatusJsonList	[     status: Integer     description: String     id: Integer }	<ul> <li>Status: the http response code for this specific ID</li> <li>Description: the description</li> <li>Id: the ID of the object for this specific response</li> </ul>



# 9.4.4 Dictionary Attribute Delete API

The  $\langle ARM\_Configurator\_IP \rangle /ARM/v1/identity/dicAttribute/{id} URL when used with the DELETE method, provides the ability for the ARM Manager to send a request to the ARM Configurator to delete a Dictionary attribute.$ 

#### **REST Resource**

<ARM Configurator\_IP>/ARM/v1/identity/dicAttribute/{id}

Where {id} is the ID of the element in the database.

#### For multiple delete actions:

<ARM\_Configurator\_IP>/ARM/v1/identity/dicAttribute?filter=(id=id1;
id2;...)

#### **HTTP Method**

DELETE

#### **Supported Content-Type**

application/json

### **Attributes (Multi-delete)**

Attribute	Туре	Description
multiStatusJsonList	{     status: Integer     description: String     id: Integer }	Status: the http response code for this specific ID Description: the description Id: the ID of the object for this specific

#### **HTTP Response**

The response will be a multi-response JSON with one of the following response codes for each ID that is sent:

- 409 Conflict
- 500 Internal Error

Developer's Guide 9. Identity

# 9.4.5 File Repository Delete API

The <code><ARM\_Configurator\_IP>/ARM/v1/identity/fileRepository/{id}</code> URL when used with the DELETE method, provides the ability for the ARM Manager to send a request to the ARM Configurator to delete a specific File Repository.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/identity/fileRepository/{id}

### **HTTP Method**

DELETE

# **Supported Content-Type**

application/json



# 10 Statistics REST API

This chapter describes the REST API resources for ARM statistics.

# 10.1 Get Report API

ARM provides an API for retrieving reports.

#### **REST Resource**

<ARM\_Configurator\_IP>/v1/statistics/report/<report\_identifier>?fil
ter=(dateType=RANGE,startDate=1542492000,endDate=1542578340,statis
tics=SOURCE CALL ATLTERNATIVE ROUTING ATTEMPTS )

### **HTTP Method**

GET

### **Supported Content-Type**

application/json

filter	Туре	Description
reportIdentifier <report_identifier> in the url</report_identifier>	ReportIdentifier	ReportIdentifier: armOverTime, nodeOverTime, topNodes, topNodesOverTime, nodeStackedByPeerConnection, topNodesStckedByPeerConnection, peerConnectionOverTime, topPeerConnections, topPeerConnectionsOverTime, connectionOverTime, topConnectionsOverTime, routerOverTime, topRouters, topRoutersOverTime, routingGroupOverTime, ropRoutingGroupStackedByRoutingRules, topRoutingGroupsStackedByRoutingRules, routingRuleOverTime, topRoutingRulesOverTime, routingRuleStackedByActions, topRoutingRuleStackedByActions;
dateType	DateType	DateType: RANGE,

Developer's Guide 10. Statistics REST API

filter	Туре	Description
		RELATIVE; Must
startDate	Long	unix time in seconds  Must when DateType is RANGE
endDate	Long	unix time in seconds  Must when DateType is RANGE
relativeTimeUnit	TimeUnit	TimeUnit:  MONTH, WEEK, DAY, HOUR, MINUTE; Must when DateType is RELATIVE
relativeTimeUnitValue	Integer	Must when DateType is RELATIVE
numberOfElements	Integer	
elements	[ Integer ]	IDs of selected elements.
statistics	Array of StatisticType	StatisticsType: SOURCE_CALL_1ST_ROUTING_ATT EMPTS, SOURCE_CALL_ATLTERNATIVE_RO UTING_ATTEMPTS, SOURCE_CALL_FAILED_ROUTING_A TTEMPTS, SOURCE_CALL_DISCARD_ROUTING _ATTEMPTS, DESTINATION_CALL, TRANSIENT_CALL,ss ROUTING_RULE_ACTION_1ST_MATC H, ROUTING_RULE_ACTION_2ND_MAT CH, ROUTING_RULE_ACTION_3RD_MAT CH, SOURCE_CALL_DROP_ROUTING_RE QUEST, ROUTING_RULE_ACTION_TRY, ROUTING_RULE_ACTION_FAIL, NO_MATCH_RULE; Must
overTimeGraphType	OverTimeGraphType	OverTimeGraphType: MULTUPLE_STATISTICS, MULTUPLE_ELEMENTS;  Must only in reports over time (except from ARM over time).  Multiple statistics- means few statistics on one element.



filter	Туре	Description
		Multiple elements – means few elements on one statistic.

### Response:

Response:		
Attribute	Туре	Description
data	{     "startDate": Long,     "interval": Integer,     "series": [     {         "elementName": String,         "statisticName": String,         "data": [         {             "name": String,             "id": Integer,             "y": Long         }         ]         }         ]     }     ] }	Interval should be in seconds.  The order in series. Data list is important in case of over time graph.  The first point in the data array representing the start date and each point after it is the previous date + interval.
title	String	
Subtitle	String	
graphType	GraphType	GraphViewType: COLUMN, LINE, STACKED_COLUMN;
preferences		This is in case we will want to add more information in the future.

- 200 OK
- 409 Conflict
- 500 Internal Error

Developer's Guide 10. Statistics REST API

# 10.1.1 Top Routes Statistics

The <code><ARM\_Configurator\_IP>/ARM/v1/</code> performanceMonitoring/topRoutes? filter=(startTime={startTime}, endTime={endTime}) URL when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve top routes. Top routes represent the busiest routes for a period of time.

#### **REST Resource**

```
<ARM_Configurator_IP>/ARM/v1/ performanceMonitoring/topRoutes?
filter=(startTime={startTime}, endTime={endTime})
{ startTime } - unix time (seconds)
{endTime} - unix time (seconds)
```

#### **HTTP Method**

GET

# **Supported Content-Type**

application/json

# **Response Attributes**

Attribute	Туре	Description
Top Routes	ARRAY OF: [  {     startTime: integer     endTime: integer     startTimeTs: String     endTimeTs: String     dataValid: boolean     routes:     [         {             route: String             srcNode: integer             srcPeerConnection: integer             destPeerConnection: integer (optional)     destPeerConnection: integer (optional)     hits:integer	The query elements for the node upon which the data is collected.
	edges:[ (optional) {	



Attribute	Туре	Description
	}	
	1	
	}	
	1	
	1	

Developer's Guide 10. Statistics REST API

# 10.1.1.1 Filter

The statistics API requires using a filter to control the size and content of the data. The filter should be added to the suffix of the URL, for example:

#### **REST Resource**

```
<ARM_Configurator_IP>/ARM/v1/
performanceMonitoring/topRoutes?filter=(startTime={startTime},endT
ime={endTime}mmaxRoutes={max routes})
```

### **HTTP Method**

GET

# **Supported Content-Type**

application/json

# **Response Attributes**

Filter	Available for these requests	Description
startTime	For all resources	Results data timestamp beginning from startTime. Where startTime is the unix time in seconds.
endTime	For all resources	Results data timestamp ending by endTime. Where endTime is the unix time in seconds.
maxRoutes	For all resources	The maximum number of routes to return.

- 200 OK
- 409 Conflict
- 500 Internal Error



This page is intentionally left blank.

Developer's Guide 11. Alarms History

# 11 Alarms History

This chapter describes the REST API resources for the Alarms History.

# 11.1 Get API

The <code><ARM\_Configurator\_IP>/ARM/v1/alarms/history</code> URL when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve alarm events.

#### **REST Resource**

```
<ARM_Configurator_IP>/ARM/v1/alarms/history
<ARM Configurator IP>/ARM/v1/alarms/history/{id}
```

Where {id} is the ID of a specific event.

#### **HTTP Method**

GET

### **Supported Response Attributes**

The following attributes MUST be included:

Attribute	Туре	Description
id	Integer	The internal ID of the alarm in the database.
alarmDateAndTime	Date	The time that the ARM Configurator raised the alarm. In the following format: 2010-03-01T22:38:37.000Z (UTC time)
name	String	The name of the alarm For example: "Operation status changed"
alarmSource	String	The source of the alarm
alarmSeverity	Integer	The alarm severity:  0 = cleared  1 = indeterminate  2 = warning  3 = minor  4 = major  5 = critical
alarmType	Integer	The alarm type:  0 = other  1 = communicationsAlarm  2 = qualityOfServiceAlarm  3 = processingErrorAlarm  4 = equipmentAlarm  5 = environmentalAlarm



Attribute	Туре	Description
		6 = integrityViolation 7 = operationalViolation 8 = physicalViolation 9 = securityServiceOrMechanismViolation 10 = timeDomainViolation
alarmProbCause	Integer	The probable cause of the alarm.
alarmTextualDescription	String	The text description of the alarm.
alarmAddInfo1	String	The additional information for the alarm received in the AddInfo1 field.
alarmAddInfo2	String	The additional information for the alarm received in the AddInfo2 field.
alarmAddInfo3	String	The additional information for the alarm received in the AddInfo3 field.
nodeld	Integer	The ID of the node where the alarm is raised.
routingInterfaceId	Integer	The routing interface ID of the alarm.
alarmUniqId	Integer	The internal ID of the alarm in the database.
isAlarm	Boolean	Indicates whether an alarm or an event.
clearedBy	Integer	Indicates which event cleared the alarm (Optional)

- 409 Conflict
- 200 OK response if at least one resource is found.
- 204 No Content Response

Developer's Guide 11. Alarms History

# 11.1.1 Get Filter API

There is a possibility to use filter for specific types of requests. The filter should be added to the suffix of the URL, for example:

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/alarms/history?filter=(severity=minor)

#### **HTTP Method**

GET

# **Supported Content-Type**

application/json

Filter	Operation	Description
searchString	contains	The search string for the filter query.  Results are retrieved only if the provided string is part of the following columns values (or operation between columns): name, source, description
name	Equals or contains	The name of the alarm specified in the filter query. Results are retrieved only if the names specified in the filter is matched.
source	contains	The alarm source specified in the filter query. The result includes only alarms whose source contains the source string defined in the filter (the source in the filter if part of the source string in the alarm).
description	contains	The alarm description specified in the filter query. Results are retrieved only if the part of the description specified in the filter is matched.
severity	equals	The severity specified in the filter query.  Results are retrieved only if the part of the severity



Filter	Operation	Description
		specified in the filter is matched.
startDate	equals	The start date for the filter query.  Results are retrieved only if the actual startDate is larger or equal to the startDate specified in the filter.
endDate	equals	The end date for the filter query.  Results are retrieved only if the actual endDate is less or equal to the endDate specified in the filter.
isAlarm	equals	Whether the History view shows alarms or events. By default, both alarms and events are displayed.

Developer's Guide 11. Alarms History

# 11.1.2 Cursor API

Filter	Operation	Description
before	Return the latest alarms	Returns all the alarms before this ID (larger than this ID).
after	Return the oldest alarms	Returns all the alarms after this ID (smaller than this ID).
limit	Limits the number of retrieved alarms for analysis purposes	Limits the number of results.

- 200 OK response if at least one resource is found.
- 204 No Content Response



# 11.1.3 Get Event Count API

The  $\ARM_Configurator_IP>/ARM/v1/alarms/history/count$  URL when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve the number of history alarms.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/alarms/history/count

#### **HTTP Method**

GET

### **Supported Content-Type**

application/json

#### **Attributes**

The following attributes MUST be included:

Attribute	Туре	Description
SeverityCount	ARRAY OF: [     {       type: AlarmSeverity,       count: Long     } ]	AlarmSeverity:     cleared     indeterminate     warning     minor     major     critical

**Note:** The absence of a count record for a specific severity, implies that there are no alarms for this type.

#### **Cursor API**

Filter	Operation	Description
before	Return the latest alarms	Returns all the events before this ID (larger than this ID).
after	Return the oldest alarms	Returns all the events after this ID (smaller than this ID).
limit	Limit the number of retrieved alarms for analysis purposes.	Limits the number of the results.

- 200 OK response if at least one resource is found
- 204 No Content Response

Developer's Guide 11. Alarms History

This page is intentionally left blank.



# 12 Active Alarms

This chapter describes the REST API resources for the Active Alarms.

# 12.1 Get API

The <ARM\_Configurator\_IP>/ARM/v1/alarms/active URL when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve a list of active alarms or a specific alarm event.

#### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/alarms/active
<ARM Configurator IP>/ARM/v1/alarms/active/{id}

Where {id} is the ID of the requested event.

#### **HTTP Method**

GET

### **Supported Content-Type**

application/json

#### **Attributes**

The following attributes MUST be included:

Attribute	Туре	Description
id	Integer	The internal ID of the alarm in the database.
alarmDateAndTime	Date	The time and date that the ARM Configurator raised the alarm.
		In the following format:
		2010-03-
		01T22:38:37.000Z
		(UTC time)
name	String	The name of the alarm
		For example:
		"Operation status changed"
alarmSource	String	The source of the alarm
alarmSeverity	Integer	The alarm severity
alarmType	Integer	The alarm type
alarmProbCause	Integer	The probable cause of the alarm.

Developer's Guide 12. Active Alarms

Attribute	Туре	Description
alarmTextualDescription	String	The text description of the alarm.
alarmAddInfo1	String	The additional information for the alarm received in the AddInfo1 field.
alarmAddInfo2	String	The additional information for the alarm received in the AddInfo2 field
alarmAddInfo3	String	The additional information for the alarm received in the AddInfo3 field
nodeld	Integer	The ID of the node where the alarm is raised.
routingInterfaceId	Integer	The routing interface ID of the alarm.
alarmUniqId	Integer	The internal ID of the alarm in the database.
isAlarm	Boolean	Indicates whether this is an alarm.
clearedBy	Integer	(Optional) Indicates which event was cleared by the alarm.

- 409 Conflict
- 200 OK response if at least one resource is found
- 204 No Content Response



# 12.1.1 Get Filter API

You can use a filter for specific requests. The filter should be added to the suffix of the URL, for example:

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/alarms/active?filter=(severity=minor)

#### **HTTP Method**

GET

# **Supported Content-Type**

application/json

Filter	Operation	Description
searchString	contains	The search string for the filter query.  Results are retrieved only if the provided string is part of the following columns values (or operation between columns): name, source, description
name	equals or contains	The name of the alarm specified in the filter query.  Results are retrieved only if the names specified in the filter is matched.
source	contains	The alarm source specified in the filter query.  Results are retrieved only if the part of the alarm source specified in the filter is matched.
description	contains	The alarm description specified in the filter query.  Results are retrieved only if the part of the description specified in the filter is matched.
severity	equals	The severity specified in the filter query.  Results are retrieved only if the part of the severity specified in the filter is matched.
startDate	equals	The start date for the filter query.  Results are retrieved only if the actual startDate is larger or equal to the startDate specified in the filter.
endDate	equals	The end date for the filter query.  Results are retrieved only if the actual endDate is less or equal to the endDate specified in the filter.
isAcknowledged	equals	Return only if the alarm was acknowledged by the operator.

Developer's Guide 12. Active Alarms

# 12.1.2 Cursor API

Filter	Operation	Description
before	Return the latest alarms	Returns all the events before this ID (larger than this ID).
after	Return the oldest alarms	Returns all the events after this ID (smaller than this ID).
limit	Limit the number of retrieved alarms for analysis purposes.	Limits the number of the results.

- 200 OK response if at least one resource is found
- 204 No Content Response



# 12.1.3 Get Alarm Count API

The <code><ARM\_Configurator\_IP>/ARM/v1/alarms/active/count URL</code> when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve the number of active alarms.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/alarms/active/count

#### **HTTP Method**

GET

### **Supported Content-Type**

application/json

#### **Attributes**

The following attributes MUST be included:

Attribute	Туре	Description
SeverityCount	ARRAY OF: [ {     type: AlarmSeverity,     count: Long }	AlarmSeverity:     cleared     indeterminate     warning     minor     major     critical

### **HTTP Response**

200 OK response if at least one resource is found

**Note:** The absence of a count record for a specific severity, implies that there are no alarms for this type.

Developer's Guide 12. Active Alarms

# 12.2 Update API

The  $\ARM_Configurator_IP>/ARM/v1/alarms/active/{id}$  URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to update the Active alarms.

#### **REST Resource**

PUT <ARM Configurator IP>/ARM/v1/alarms/active/{id}

Where {id} is the ID of the requested event.

### **HTTP Method**

PUT

### **Supported Content-Type**

application/json

### Attributes

The following attributes MUST be included:

Attribute	Туре	Description
isAcknowledged	Boolean	Whether the alarm was acknowledged by the operator.

- 409 Conflict in the absence of an ID
- 200 OK response if at least one resource is found.



This page is intentionally left blank.

# 13 Alarms Additional Info

This section describes the URLs for supporting the customization of information provided in notifications for call matching a specific rule (Routing Rule Match), usually applied for emergency calls such as 911 calls e.g. user name, building, floor, country or office branch name. This information is not part of the SIP INVITE message but can be added to the ARM users database and used for additional information in notifications.

# 13.1 Get Alarms Additional Info

#### **REST Resource**

GET <ARM\_Configurator\_IP>/ARM/v1/alarms/additionalInfo
GET <ARM\_Configurator\_IP>/ARM/v1/alarms/additionalInfo/{id}

#### **HTTP Method**

GET

### **Supported Content-Type**

application/json

Attribute	Туре	Description
id	Integer	The SNMP alarm OID
eventType	Integer	The event type
matchingProperty	MatchingProperty	MatchingProperty:  0 = SRC_URI_NAME  1 = SRC_URI_USER  2 = SRC_URI_HOST  3 = DST_URI_NAME  4 = DST_URI_USER  5 = DST_URI_HOST  6 = SRC_IP_FROM_LYNC
matchingMethod	MatchingMethod	MatchingMethod: 0 = FULL 1 = CONTAINS 2 = NETWORK_MASK



Attribute	Туре	Description
matchedProperty	Integer	The property ID in the database.
template	String	The text contained in the additional info pattern.
isEnabled	Boolean	Indicates if this rule match\additional info is enabled
eventName	String	The event name

# 13.2 Test Alarms Additional Info

The  $\ARM_Configurator_IP>/ARM/v1/alarms/additionalInfo/test$  API when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to test alarms Additional Info.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/alarms/additionalInfo/test

#### **HTTP Method**

PUT

### **Supported Content-Type**

application/json

Attribute	Туре	Description	
eventType	Integer (default 15)	The event type	
matchingProperty	MatchingProperty	MatchingProperty:  0 = SRC_URI_NAME  1 = SRC_URI_USER  2 = SRC_URI_HOST  3 = DST_URI_NAME  4 = DST_URI_USER  5 = DST_URI_HOST  6 = SRC_IP_FROM_LYNC	
matchingMethod	MatchingMethod	MatchingMethod: 0 = FULL 1 = CONTAINS 2 = NETWORK_MASK	
matchedProperty	Integer	The property ID in the data base.	
template	String	Default value: "" (empty string)	
eventName	String (default Routing Rule Match)	The event name	
testValue	String	Test result for GET	



This page is intentionally left blank.

Developer's Guide 14. Syslog

# 14 Syslog

This chapter describes the REST API resources for the Syslog server. The following APIs are described:

- Get API
- Create API
- Update SNMP Target API
- Delete API

# 14.1 Get API

The <ARM\_Configurator\_IP>/ARM/v1/externals/syslog URL when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve the entire syslog or a specific syslog record.

#### **REST Resource**

```
<ARM_Configurator_IP>/ARM/v1/externals/syslog
<ARM Configurator IP>/ARM/v1/externals/syslog/{id}
```

#### Where:

{id} is the ID of the requested element.

#### **HTTP Method**

GET

#### **Supported Content-Type**

application/json

#### **Attributes**

The following attributes MUST be included:

Attribute	Туре	Description
syslog	ARRAY OF: [     {     id: Integer     host: String     protocol: String     enabled: Boolean     sourceType: String     level:String     port:Integer     } ] cdrFormat: CdrType	<ul> <li>Protocol: UDP or TCP</li> <li>Enabled: Whether the syslog is enabled</li> <li>sourceType: the source of the syslog either TOPOLOGY(0) or ROUTER(1)</li> <li>level: the detail level of the syslog, enum: TRACE,DEBUG,INFO,WARN,ERROR</li> <li>CdrType enum: CDR_AS_CLEAR_TEXT, CDR_AS_JSON, BOTH</li> </ul>



## **HTTP Response:**

- 409 Conflict status for a non-existent ID.
- 200 OK response if at least one resource is found.

# 14.1.1 Get Filter

You can use a filter for specific requests. The filter should be added to the suffix of the URL, for example:

#### **REST Resource**

GET <ARM\_Configurator\_IP>/ARM/
v1/externals/syslog?filter=(sourceType=ROUTER)

#### **HTTP Method**

GET

# **Supported Content-Type**

application/json

#### **Attributes**

The following attributes MUST be included:

Filter	Available for these Requests	Description
sourceType	syslog	Returns the requested source type.

Developer's Guide 14. Syslog

# 14.2 Create API

The  $\ARM_Configurator_IP>/ARM/externals/syslog$  URL when used with the POST method creates a syslog.

## REST Resource

<ARM Configurator\_IP>/ARM/externals/syslog

## **HTTP Method**

POST

# **Supported Content-Type**

application/json

#### **Attributes**

The request MUST contain JSON data that consists of the following elements:

Attribute	Туре	Description
host	String	The IP address of the remote
port	Integer	Valid port number
protocol	String	Either UDP or TCP
enabled	Boolean	Whether the syslog is enabled or not
sourceType	String	The source of the syslog either TOPOLOGY(0) or ROUTER(1)
level	String	level: the detail level of the syslog, enum: TRACE,DEBUG,INFO,WARN,ERROR

- 201 Created
- 409 Conflict status for a non-existent ID.
- 500 Internal error



# 14.3 Update API

The  $\ARM_Configurator_IP>/ARM/externals/syslog/$  URL when used with the PUT method updates a Syslog record.

# **REST** Resource

<ARM\_Configurator\_IP>/ARM/externals/syslog/{id}

## **HTTP Method**

PUT

The request MUST contain JSON data that consists of the following elements:

Attribute	Туре	Description
host	String	The IP address of the remote host
port	Integer	The valid port number.
protocol	String	The protocol:  UDP TCP
enabled	Boolean	Whether the syslog is enabled
sourceType	String	The source of the syslog:  0 = TOPOLOGY  1 = ROUTER
level	String	The detailed level of the syslog, enum: TRACE,DEBUG,INFO,WARN,ERROR

- 200 OK
- 409 Conflict status for a non-existent ID.
- 500 Internal error

Developer's Guide 14. Syslog

# 14.4 Delete API

The <code><ARM\_Configurator\_IP>/ARM/v1/externals/syslog/{id}</code> URL enables you to delete a syslog.

# **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/externals/syslog/{id}

## **HTTP Method**

DELETE

# **Supported Content-Type**

application/json

# **HTTP Response**

200 OK response if at least one resource is found.



# 15 SNMP

This chapter describes the REST API resources for SNMP Managers. The following APIs are described:

- Get API
- Create SNMP Target API
- Update SNMP Target API
- Delete SNMP Target API

# 15.1 Get API

The  $\ARM_Configurator_IP>/ARM/v1/externals/snmp/target/$  URL when used with the GET method, URL provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve SNMP Managers.

#### **REST Resource**

```
<ARM_Configurator_IP>/ARM/v1/externals/snmp/target/
<ARM Configurator IP>/ARM/v1/externals/snmp/target/{id}
```

Where {id} is the ID of the requested element.

#### **HTTP Method**

GET

#### **Supported Content-Type**

application/json

#### **Attributes**

Attribute	Туре	Description
snmp	ARRAY OF: [     {     id: Integer     host: String     port: Integer     community: String     } ]	The SNMP Manager elements.

- 409 Conflict when an ID is not included in the request.
- 200 OK response if at least one resource is found.

Developer's Guide 15. SNMP

# 15.2 Create SNMP Target API

The  $\ARM_Configurator_IP>/ARM/v1/externals/snmp/target$  URL when used with the POST method creates a target SNMP Manager.

#### **REST Resource**

<ARM Configurator\_IP>/ARM/v1/externals/snmp/target

## **HTTP Method**

POST

# **Supported Content-Type**

application/json

#### **Attributes**

The request MUST contain JSON data that consists of the following elements:

Attribute	Туре	Description
host	STRING	Valid IP address of the SNMP Manager
port	INTEGER	Valid port of the SNMP Manager
community	STRING	The SNMPv2 community string "password"

- 201 Created
- 409 Conflict status for a non-existent ID.
- 500 Internal error



# 15.3 Update SNMP Target API

The  $\ARM_Configurator_IP>/ARM/v1/externals/snmp/target/{id}URL$  when used with the PUT method updates the details of an SNMP Manager.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/externals/snmp/target/{id}

Where {id} is the ID of the element in the database.

#### **HTTP Method**

PUT

#### **Attributes**

The request MUST contain JSON data that consists of the following elements:

Attribute	Туре	Description
host	STRING	Valid IP address of the SNMP Manager
port	INTEGER	Valid port of the SNMP Manager
community	STRING	The SNMPv2 community string "password".

# **HTTP Response**

- 200 OK
- 409 Conflict status for a non-existent ID.
- 500 Internal error

# 15.4 Delete SNMP Target API

The  $\ARM_Configurator_IP>/ARM/v1/externals/snmp/target/{id}$  URL provides the ability for the ARM Manager to send a request to the ARM Configurator to delete a Target SNMP Manager.

# REST Resource

<ARM\_Configurator\_IP>/ARM/v1/externals/snmp/target/{id}

Where {id} is the ID of the element in the database.

#### **HTTP Method**

DELETE

# **Supported Content-Type**

application/json

# **HTTP Response**

200 OK

Developer's Guide 15. SNMP

This page is intentionally left blank.



# 16 External Alarms

This chapter describes the URLs for creating external alarms for third-party proprietary equipment such as routers and for third-party applications such as Web Services.

# 16.1 Create External Alarm

The <arm\_Configurator\_IP>/ARM/v1/externals/alarm URL when used with the POST method, provides the ability for the ARM Manager to send a request to the ARM Configurator to create a single external alarm.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/externals/alarm

#### **HTTP Method**

POST

## **Supported Content-Type**

application/json

#### **Attributes**

The request MUST contain JSON data that consists of the following elements:

Attribute	Туре	Description
source	STRING	SNMP Alarm source
identifier	STRING	SNMP Alarm OID
description	STRING	Alarm description field
addInfo1		The additional information for the alarm received in the AddInfo1 field.
addInfo2		The additional information for the alarm received in the AddInfo2 field.
severity	AlarmSeverity	AlarmSeverity:  0 = cleared  1 = indeterminate  2 = warning  3 = minor  4 = major  5 = critical
alarmType	AlarmEventType	AlarmEventType:  0 = other  1 = communicationsAlarm  2 = qualityOfServiceAlarm  3 = processingErrorAlarm  4 = equipmentAlarm  5 = environmentalAlarm  6 = integrityViolation

Developer's Guide 16. External Alarms

Attribute	Туре	Description
		7 = operationalViolation 8 = physicalViolation 9 = securityServiceOrMechanismViolation 10 = timeDomainViolation
probabyCause	AlarmProbableCause	AlarmProbableCause:  0 = other  1 = adapterError  2 = applicationSubsystemFailure  3 = bandwidthReduced  4 = callEstablishmentError  5 = communicationsProtocolError  6 = communicationsSubsystemFailure  7 = configurationOrCustomizationError  8 = congestion  9 = corruptData  10 = cpuCyclesLimitExceeded  11 = dataSetOrModemError  12 = degradedSignal  13 = dteDceInterfaceError  14 = enclosureDoorOpen  15 = equipmentMalfunction  16 = excessiveVibration  17 = fileError  18 = fireDetected  19 = floodDetected  20 = framingError  21 = heatingVentCoolingSystemProblem  22 = humidityUnacceptable  23 = inputOutputDeviceError  24 = inputDeviceError  25 = lanError  26 = leakDetected  27 = localNodeTransmissionError  28 = lossOfFrame  29 = lossOfSignal  30 = materialSupplyExhausted  31 = multiplexerProblem  32 = outOfMemory  33 = ouputDeviceError  34 = performanceDegraded  35 = powerProblem  36 = pressureUnacceptable  37 = processorProblem  38 = pumpFailure  39 = queueSizeExceeded  40 = receiveFailure  41 = receiverFailure  42 = remoteNodeTransmissionError  43 = resourceAtOrNearingCapacity  44 = responseTimeExecessive  45 = retransmissionRateExcessive
		46 = softwareError



Attribute	Туре	Description
		47 = softwareProgramAbnormallyTerminated
		48 = softwareProgramError
		49 = storageCapacityProblem
		50 = temperatureUnacceptable
		51 = thresholdCrossed
		52 = timingProblem
		53 = toxicLeakDetected
		54 = transmitFailure
		55 = transmitterFailure
		56 = underlyingResourceUnavailable
		57 = versionMismatch
		58 = authenticationFailure
		59 = breachOfConfidentiality
		60 = cableTamper
		61 = delayedInformation
		62 = denialOfService
		63 = duplicateInformation
		64 = informationMissing
		65 = informationModificationDetected
		66 = informationOutOfSequence
		67 = intrusionDetection
		68 = keyExpired
		69 = nonRepudiationFailure
		70 = outOfHoursActivity
		71 = outOfService
		72 = proceduralError
		73 = unauthorizedAccessAttempt
		74 = unexpectedInformation

Developer's Guide 16. External Alarms

# 16.2 Create Multiple External Alarms

The <code><ARM\_Configurator\_IP>/ARM/v1/externals/alarms</code> URL when used with the POST method, provides the ability for the ARM Manager to send a request to the ARM Configurator to create multiple external alarms.

## **REST Resource**

<ARM Configurator IP>/ARM/v1/externals/alarms

#### **HTTP Method**

POST

## **Supported Content-Type**

application/json

## **Attributes**

The request MUST contain JSON data that consists of the following elements:

Attribute	Туре	Description
<pre>[     source: String     identifier: String     description: String     addInfo1: String     addInfo2: String     severity: AlarmSeverity     alarmType: AlarmEventType     probabyCause: AlarmProbableCause } ]</pre>		



# 17 Normalization Group

This chapter describes the REST resources for the Normalization Group API (Attribute Manipulation Group). The following APIs are described:

- Get API
- Create Normalization Group API
- Update Normalization Group Target API
- Delete Normalization Group API
- Test Normalization Group
- Get Normalization Group Associations (Relationships)

# 17.1 Get API

The <arm\_Configurator\_IP>/ARM/v1/normalization/group URL when used with the GET method provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve Normalization Groups.

#### **REST Resource**

```
<ARM_Configurator_IP>/ARM/v1/normalization/group
<ARM_Configurator_IP>/ ARM/v1/normalization/group/{id}
```

Where {id} is the ID of the element in the database.

#### **HTTP Method**

GET

# **Supported Content-Type**

application/json

#### **Attributes**

Attribute	Туре	Description
normalizationGroup	ARRAY OF:  [  id: Integer groupName: String normalizationAttrs: [  id: Integer priority: Integer regExp: String	<ul> <li>Priority – the priority of the attribute inside the group</li> <li>regEx – regular expression that will be matched against the element</li> <li>replacement – the value to replace with the matched expression</li> </ul>

Attribute	Туре	Description
	replacement: String	
	url: String	
	}	
	]	
	}	
	1	

- 409 Conflict when an ID is not contained in the request.
- 200 OK



# 17.2 Create Normalization Group API

The  $\ARM_Configurator_IP>/ARM/v1/normalization/group\ URL$  when used with the POST method provides the ability for the ARM Manager to send a request to the ARM Configurator to create a Normalization Group.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/normalization/group

#### **HTTP Method**

POST

## **Supported Content-Type**

application/json

#### **Attributes**

The request MUST contain JSON data that consists of the following elements:

Attribute	Туре	Description
groupName	STRING	The name of the group must be unique.
normalizationAttrs [ {     priority: Integer     regEx: String     replacement: String }		<ul> <li>priority – the priority of the attribute inside the group</li> <li>regEx – regular expression that will be matched against the element</li> <li>replacement – the value to replace with the matched expression.</li> </ul>

- 201 Created
- 409 Conflict
- 500 Internal Error

# 17.3 Update Normalization Group Target API

The  $\ARM_Configurator_IP>/ARM/v1/normalization/group/{id}$  URL when used with the PUT method, updates the details of a Normalization Group.

#### REST Resource

<ARM Configurator IP>/ARM/v1/normalization/group/{id}

Where {id} is the ID of the element in the database.

## **HTTP Method**

PUT

## **Supported Content-Type**

application/json

#### **Attributes**

The request MUST contain JSON data that consists of the following elements:

Attribute	Туре	Description
groupName	STRING	The name of the group, must be unique
normalizationAttrs [     {         Id: Integer         priority: Integer         regEx: String         replacement: String     } ]		<ul> <li>Id – the ID of the attribute as received in the get request</li> <li>regEx – regular expression that will be matched against the element</li> <li>replacement – the value to replace with the matched expression</li> </ul>

#### **HTTP Response**

- 200 OK
- 409 Conflict
- 500 Internal Error

**Note:** To delete the normalization attribute, the update request should be sent to the group, without the attribute you wish to delete.



# 17.4 Delete Normalization Group API

The  $\ARM_Configurator_IP>/ARM/v1/normalization/group/{id} URL provides the ability for the ARM Manager to send a request to the ARM Configurator to delete a Normalization Group.$ 

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/normalization/group/{id}

Where {id} is the ID of the element in the database.

#### **HTTP Method**

DELETE

## **Supported Content-Type**

application/json

- 409 Conflict if the Group is connected to other elements
- 200 OK

# 17.5 Test Normalization Group

The  $\ARM_Configurator_IP>/ARM/v1/normalization/group/test$  URL when used with the POST method, tests a Normalization Group over random input (Rules Simulation for Attribute Manipulation Group).

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/normalization/group/test

#### **HTTP Method**

POST

#### **Supported Content-Type**

application/json

# **Request Attributes**

The request MUST contain JSON data that consists of the following elements:

Attribute	Туре	Description
testString	String	The string which the manipulation will be done on
normalizationAttrs [     {        priority: Integer       regEx: String     replacement: String     } ]		<ul> <li>regEx – regular expression that will be matched against the element</li> <li>replacement – the value to replace with the matched expression.</li> </ul>

## **Response Attributes**

The response MUST contain JSON data that consists of the following elements:

Attribute	Туре	Description
result	String	The result of the normalization on the "testString" field
results:[ {     regEx: String     result: String }		The intermediate results of each replacement done according to the regular expression

- 409 Conflict when there is an error regarding the syntax of the regular expressions (including error description)
- 200 OK



# **17.5.1 Examples**

The operator may wish to test an existing normalization group, where this may be performed by sending the following HTTP request:

POST <ARM Configurator IP>/ARM/v1/normalization/group/{id}/test

Where {id} is the ID of the element in the database.

# **Request Attribute**

Attribute	Туре	Description
testString	String	The string upon which the manipulation will be performed.

# **Response Attributes**

Attribute	Туре	Description
result	String	The result of the normalization on the "testString" field
results:[ {   regEx: String   result: String }		The intermediate results of each replacement performed according to the regular expression.

# **HTTP Response**

200 OK

# 17.6 Get Normalization Group Associations (Relationships)

#### The

<ARM\_Configurator\_IP>/ARM/v1/normalization/group/{id}/associations
URL when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve the Normalization Group Associations (Relationships). This request provides details of the relationships of a normalization group to different elements in the system, such as routing rules and peer connections.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/normalization/group/{id}/associations

#### **HTTP Method**

GET

# **Supported Content-Type**

application/json

#### **Attributes**

Attribute	Туре	Description
{   routingRules: [   Integer   ],		<ul> <li>routingRules – ids of the routing rules to which the normalization group is associated.</li> </ul>
}		

## **HTTP Response**

200 OK



This page is intentionally left blank.

# 18 NTP Server Rest API

This chapter describes the REST resources for the NTP server. The following APIs are described:

- Get API
- Create NTP Server
- Update NTP Server
- NTP Server Delete API

# 18.1 Get API

The <arm\_Configurator\_IP>/ARM/v1/ntpServer when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve NTP servers.

#### **REST Resource**

```
<ARM_Configurator_IP>/ARM/v1/ntpServer
<ARM Configurator IP>/ARM/v1/ntpServer/{id}
```

Where {id} is the ID of the element in the data.

#### **HTTP Method**

GET

#### **Supported Content-Type**

application/json

#### **Attributes**

The ARM Configurator must respond to the Get request with JSON data from the request URI element and its ID. If the ID was not specified in the Get request URI, JSON data must contain an array of all specified elements defined in the database.

The following attributes MUST be included:

Attribute	Туре	Description
Server	ARRAY OF: [	IP address or FDQN of the NTP server.

# **HTTP Response**

200 OK



# 18.2 Create NTP Server

The  $\ARM_Configurator_IP>/ARM/v1/ntpServer$  URL when used with the POST method, provides the ability for the ARM Manager to send a request to the ARM Configurator to create an NTP server.

## **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/ntpServer

#### **HTTP Method**

POST

## **Supported Content-Type**

application/json

## **Attributes**

The request MUST contain JSON data that consists of the following elements:

Attribute	Туре	Description
serverName	String	Name of the NTP server.
address	String	IP Address of the NTP server.

# **HTTP Response**

201 Created

# 18.3 Update NTP Server

The  $\ARM_Configurator_IP>/ARM/v1/ntpServer/{id}$  URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to update an NTP server.

# REST Resource

<ARM Configurator IP>/ARM/v1/ntpServer/{id}

Where {id} is the ID of the element in the database.

## **HTTP Method**

PUT

# **Supported Content-Type**

application/json

## Attributes

The request must contain the following data elements:

Attribute	Туре	Description
serverName	String	Name of the NTP server.
address	String	IP address of the NTP server.

# **HTTP Response**

200 OK



# 18.4 NTP Server Delete API

The  $\ARM_Configurator_IP>/ARM/v1/ntpServer/{id}URL$  when used with the DELETE method provides the ability for the ARM Manager to send a request to the ARM Configurator to delete an NTP server.

#### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/ntpServer/{id}

Where {id} is the ID of the element in the database.

#### **HTTP Method**

DELETE

# **Supported Content-Type**

application/json

## **HTTP Response**

200 OK

Developer's Guide 19. ARM License

# 19 ARM License

This chapter describes the REST resources for the ARM License. The following APIs are described:

- Get License API
- Get ARM Machine ID
- Update License Key API

# 19.1 Get License API

The  $\ARM_Configurator_IP>/ARM/v1/license/key$  URL when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve an ARM License.

## **REST Resource**

<ARM Configurator IP>/ARM/v1/license/key

## **HTTP Method**

GET

# **Supported Content-Type**

application/json

# **Response Attributes**

The response should be as follows:

Attribute	Туре	Description
url	String	The URL of the ARM license.
license	String	The ARM license string.
machineld	String	The machine ID of the ARM Configurator.
limitedByDate	boolean	Whether the license expires according to a specific date.
licenseDate { day: String, month: String, year: String }		The license date.  Can be null if limitedByDate is false.



Attribute	Туре	Description
Features [ {     feature: String,     value: String }		Array of license features
licenseExists	Boolean	Whether license exists.

- 200 OK
- 409 Conflict
- 500 Internal Error

Developer's Guide 19. ARM License

# 19.2 Get ARM Machine ID

The <ARM\_Configurator\_IP>/ARM/v1/license/machineId URL when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve the details of a ARM Machine ID.

## **REST Resource**

<ARM Configurator IP>/ARM/v1/license/machineId

#### **HTTP Method**

GET

## **Supported Content-Type**

application/json

#### **Attributes**

Attribute	Туре	Description
machineld	String	The ARM machine ID.

- 200 OK
- 409 Conflict
- 500 Internal error



# 19.3 Update License Key API

The  $\ARM_Configurator_IP>/ARM/v1/license/key URL$  when used with the PUT method provides the ability for the ARM Manager to send a request to the ARM Configurator to update a License Key.

#### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/license/key

#### **HTTP Method**

PUT

# **Supported Content-Type**

application/json

#### **Attributes**

The request MUST contain JSON data that consists of the following elements:

Attribute	Туре	Description
license	String	The valid ARM license string.

- 200 OK
- 409 Conflict
- 500 Internal error

Developer's Guide 19. ARM License

This page is intentionally left blank.



# 20 Configuration

This chapter describes additional configuration requests for the following APIs:

- Normalization API
- License Configuration
- Routing Rule Configuration
- Security Configuration
- Quality-based Routing Configuration
- LDAP Authentication
- RADIUS Authentication
- Calls Configuration
- Registered Users
- Analytics
- Registration

# 20.1 Normalization API

This section describes additional configuration requests for the Normalization API.

# 20.1.1 Update Routing Normalization API

The <arm\_Configurator\_IP>/ARM/v1/configuration/normalization URL when used with the PUT method provides the ability for the ARM Manager to send a request to the ARM Configurator to update Routing Normalization API.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/configuration/normalization

#### **HTTP Method**

PUT

# **Supported Content-Type**

application/json

#### **Attributes**

The request MUST contain JSON data that consists of the following elements:

Attribute	Туре	Description
srcNormalization	Integer	ID of the normalization group
destNormalization	Integer	ID of the normalization group

- 200 OK response if at least one resource is found.
- 409 Conflict in case of an incorrect request.

Developer's Guide 20. Configuration

# 20.1.2 Get Routing Normalization API

The  $\ARM_Configurator_IP>/ARM/v1/configuration/normalization$  URL when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve a Normalization API.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/configuration/normalization

#### **HTTP Method**

GET

# **Supported Content-Type**

application/json

## Attributes

Attribute	Туре	Description
srcNormalization	Integer	ID of the normalization group
destNormalization	Integer	ID of the normalization group

- 200 OK response if at least one resource is found.
- 409 Conflict in case of an incorrect request.



# 20.2 License Configuration

This section describes additional configuration requests for the License API.

# 20.2.1 Get License Configuration

The <code><ARM\_Configurator\_IP>/ARM/v1/configuration/license</code> URL when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve an ARM License.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/configuration/license

#### **HTTP Method**

GET

## **Supported Content-Type**

application/json

#### Attributes

Attribute	Туре	Description
numberOfSessionsAlarmWarning	Integer	The Alarm warning threshold to indicate when the number of valid licensed sessions is exceeded (percentage)
numberOfSessionsAlarmCritical	Integer	The Alarm critical threshold to indicate when the number of valid licensed sessions is exceeded.
currentNumberOfSessions	Integer	The current number of sessions in the system.

- 200 OK response if at least one resource is found.
- 409 Conflict in case of an incorrect request.

Developer's Guide 20. Configuration

# 20.2.2 Update License Configuration

The <code><ARM\_Configurator\_IP>/ARM/v1/configuration/license</code> URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to update an ARM License.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/configuration/license

## **HTTP Method**

PUT

# **Supported Content-Type**

application/json

The request MUST contain JSON data that consists of the following elements:

Attribute	Туре	Description
numberOfSessionsAlarmWarning	Integer	The Alarm warning threshold to indicate when the number of valid licensed sessions is exceeded (percentage).

- 201 Created
- 409 Conflict in case of an incorrect request.



# 20.3 Routing Rule Configuration

This section describes additional configuration requests for the Routing Rule API.

# 20.3.1 Routing Rule Configuration

The <code><ARM\_Configurator\_IP>/ARM/v1/configuration/routingRule URL</code> when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to configure a routing rule.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/configuration/routingRule

#### **HTTP Method**

PUT

#### **Supported Content-Type**

application/json

# Attributes

Attribute	Туре	Description
maxRoutes	Integer	The maximum number of routes Default value is 6
maxRoutesPerAction	Integer	The maximum number of routes per action. Default value is 2
maxOfPconsPerVoippeer	Integer	The maximum number of peer connections per VoipPeer Default value is 2

- 201 Created
- 409 Conflict in case of an incorrect request.

# 20.3.2 Update Routing Rule Configuration

The  $\ARM_Configurator_IP>/ARM/v1/configuration/routingRule$  URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to update a routing rule.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/configuration/routingRule

### **HTTP Method**

PUT

## **Supported Content-Type**

application/json

### Attributes

Attribute	Туре	Description
maxRoutes	Integer	The maximum number of routes.  Default value is 6
maxRoutesPerAction	Integer	The maximum number of routes per action. Default value is 2
maxOfPconsPerVoippeer	Integer	The maximum number of peer connections per VoipPeer Default value is 2

## **HTTP Response**

- 201 Created
- 409 Conflict in case of an incorrect request.

**Note:** All the values must be positive between 1 and 10, otherwise 409 conflict will be returned. Values that are not sent in the JSON will not be updated.



# 20.4 Security Configuration

This section describes the security configuration.

# 20.4.1 Get Security Configuration

The <arm\_Configurator\_IP>/arm/v1/configuration/security URL when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve the security credentials of ARM users.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/configuration/security

### **HTTP Method**

GET

### **Supported Content-Type**

application/json

### Attributes

Attribute	Туре	Description
userName	String	User name that ARM uses for HTTP authentication with the devices. Default value is Admin
Password	String	Password that ARM uses for HTTP authentication with the devices. Default value is Admin
sessionTimeout	Integer	Client session timeout (in hours). Default value is Default value is 5 hours
inactivityPeriod	Integer	Client inactivity period (in minutes). Default value is 5 minutes
httpHttpsEnabled	Boolean	Whether mixed mode is on or off (http+https)
configuratorIpAddress	String	The IP address of the configurator
configuratorHostname	String	The host name of the configurator
IsConfCommunicationIpBased	Boolean	Indicates whether ARM should publish the host name or the ip address
verifyCertificate	Boolean	Indicates whether the configurator should verify the server certificate before initiating the TLS connection.
verifyCertificateSubjectName	Boolean	Indicates whether the configurator should verify the server's subject name before initiating the TLS connection.

- 200 OK
- 500 Internal error

# 20.4.2 Update Security Configuration

The <code><ARM\_Configurator\_IP>/ARM/v1/configuration/security</code> URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to update the security credentials of an ARM user.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/configuration/security

### **HTTP Method**

PUT

# **Supported Content-Type**

application/json

### Attributes

Attribute	Туре	Description
userName	String	User name that ARM uses for HTTP authentication with the devices.  Default value is 'Admin'
Password	String	Password that ARM uses for HTTP authentication with the devices.  Default value is 'Admin'
sessionTimeout	Integer	Client session timeout (in seconds). Default value is Default value is 300
inactivityPeriod	Integer	Client inactivity period (in seconds). Default value is 300
httpHttpsEnabled	Boolean	Indicates whether mixed mode (HTTP+HTTPS) is enabled or disabled.
configuratorlpAddress	String	The IP address of the configurator
configuratorHostname	String	The host name of the configurator
IsConfCommunicationIpBased	Boolean	Indicates whether ARM should publish the host name or the IP address.
verifyCertificate	Boolean	Indicates whether the configurator should verify the server certificate before initiating the TLS connection
verifyCertificateSubjectName	Boolean	Indicates whether the configurator should verify the server's subject name before initiating the TLS connection.

Note: Security configuration is only available for the Security administrator (Get/ Update).

- 200 OK
- 409 Conflict
- 500 Internal error



# 20.5 Quality-based Routing Configuration

# 20.5.1 Quality-based Routing Configuration

The <code><ARM\_Configurator\_IP>/ARM/v1/configuration/quality</code> URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to update the Quality-based routing configuration.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/configuration/quality

### **HTTP Method**

PUT

### **Supported Content-Type**

application/json

### Attributes

Attribute	Туре	Description
samplingTime	Integer	The rate in seconds in which the nodes send quality status updates This attribute also controls the rate in which the topology updates the routers regarding the quality changes  Default 60 seconds
isQualityEnabled	Boolean	Is the feature enabled or not
"ASR":{  lowerThreshold: Float  upperThreshold: Float  isUsed:Boolean }	-	ASR value:  Lower Threshold  Upper Threshold  If Used
"MOS":{     lowerThreshold: Float     upperThreshold: Float     isUsed:Boolean }		Mos value: Lower Threshold Upper Threshold If Used

- 200 OK
- 409 Conflict
- 500 Internal error

# 20.5.2 Quality-based Routing Update Configuration

The <code><ARM\_Configurator\_IP>/ARM/v1/configuration/quality</code> URL when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve the Quality-based routing configuration.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/configuration/quality

### **HTTP Method**

GET

# **Supported Content-Type**

application/json

### Attributes

Attribute	Туре	Description
samplingTime	Integer	The rate in seconds in which the nodes send quality status updates This attribute also controls the rate in which the topology updates the routers regarding the quality changes  Default 60 seconds
isQualityEnabled	Boolean	Is the feature enabled or not
"ASR":{     lowerThreshold: Float     upperThreshold: Float     isUsed:Boolean }		ASR value:  Lower Threshold  Upper Threshold  If Used
"MOS":{     lowerThreshold: Float     upperThreshold: Float     isUsed:Boolean }		Mos value: Lower Threshold Upper Threshold If Used

- 200 OK
- 409 Conflict
- 500 Internal error



# 20.6 LDAP Authentication

# 20.6.1 Get LDAP Authentication Server

The <code> <ARM\_Configurator\_IP>/ARM/v1/configuration/security/ldap URL when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve the LDAP Authentication Server attributes.</code>

#### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/configuration/security/ldap

### **HTTP Method**

GET

### **Supported Content-Type**

application/json

Attribute	Туре	Description
baseObject	String	The base object from which the search will be conducted
dn	String	The user DN to do the initial binding to the server
isEnabled	Boolean	Whether the LDAP authentication feature is activated
isSSLEnabled	Boolean	Should LDAPS be used
port	Integer	LDAP server port number
host	String	LDAP server host name
"parsedCertificate":{     issuer: String     notAfter: String     notBefore: String     subject:String     validity:String }		The parsed certificate if such certificate exists

Attribute	Туре	Description
"mappings":{     adminMapping: String     permissionsAttribute: String     securityAdminMapping: String userNameAttribute:String }		The mapping for each permission lever (Security admin and Admin). The field that the permission will be checked against and the field for the username.
certificate		
connectTimeout	Integer	
isReferralEnabled	Boolean	

- 200 OK
- 409 Conflict
- 500 Internal error



# 20.6.2 Update/Add LDAP Authentication Server

The <code> <ARM\_Configurator\_IP>/ARM/v1/configuration/security/ldap URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to Update/Add the LDAP Authentication Server attributes.</code>

### **REST Resource**

<ARM Configurator IP>/ARM/v1/configuration/security/ldap

### **HTTP Method**

PUT

## **Supported Content-Type**

application/json

### **Attributes**

Attribute	Туре	Description
baseObject	String	The base object from which the search will be conducted
dn	String	The user DN to do the initial binding to the server
isEnabled	Boolean	Whether the LDAP authentication feature is activated
isSSLEnabled	Boolean	Should LDAPS be used
port	Integer	LDAP server port number
host	String	LDAP server host name
certificate		Certificate if LDAPS is sued
"mappings":{     adminMapping: String     permissionsAttribute: String     securityAdminMapping: String     userNameAttribute:String }		The mapping for each permission lever (Security admin and Admin) The field that the permission will be checked against and the field for the username
certificate		
connectTimeout	Integer	
isReferralEnabled	Boolean	
password	String	The password for the initial binding

- 200 OK
- 409 Conflict
- 500 Internal error

# 20.6.3 Test LDAP Authentication Server

The  $\ARM_Configurator_IP>/ARM/v1/configuration/security/ldap$  URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to test the LDAP Authentication Server.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/configuration/security/ldap/test

### **HTTP Method**

PUT

# **Supported Content-Type**

application/json

### Attributes

Attribute	Туре	Description
baseObject	String	The base object from which the search will be conducted
dn	String	The user DN to do the initial binding to the server
isSSLEnabled	Boolean	Whether the LDAP authentication feature is activated
isSSL	Boolean	Should LDAPS be used
port	Integer	LDAP server port number
host	String	LDAP server host name
certificate		Certificate if LDAPS is sued
"mappings":{     adminMapping: String     permissionsAttribute: String     securityAdminMapping: String userNameAttribute:String }		The mapping for each permission lever (Security admin and Admin)  The field that the permission will be checked against and the field for the username
passsword	String	The password for the initial binding
testConnectivity:{     name:String     password:String }		The user name and the password to check against the LDAP server

- 200 OK
- 409 Conflict
- 500 Internal error



# 20.7 RADIUS Authentication

# 20.7.1 Get RADIUS Authentication Server

The  $\ARM_Configurator_IP>/ARM/v1/configuration/security/ldap$  URL when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve the RADIUS Authentication Server attributes.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/configuration/security/radius

### **HTTP Method**

GET

# **Supported Content-Type**

application/json

### Attributes

Attribute	Туре	Description
defaultRole	ENUM	SECURITY_ADMIN,ADMIN,MONITOR,REJECT The default authentication level if the RADIUS doesn't have audiocodes dictionary but the user was found in the RADIUS
isEnabled	Boolean	Whether the RADIUS authentication feature is activated
port	Integer	The pot number
host	String	The host / IP address of the RADIUS server
retryCount	Integer	The number of retries in case of the failure
sharedSecret	String	The password of the RADIUS server
timeout	Integer	The connection timeout

- 200 OK
- 409 Conflict
- 500 Internal error

# 20.7.2 Update/Add RADIUS Authentication Server

The  $\ARM\_Configurator\_IP>/ARM/v1/configuration/security/radius$  URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to update or add the RADIUS Authentication Server attributes.

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/configuration/security/radius

### **HTTP Method**

PUT

### **Supported Content-Type**

application/json

#### **Attributes**

Attribute	Туре	Description
defaultRole	ENUM	SECURITY_ADMIN,ADMIN,MONITOR,REJECT The default authentication level if the RADIUS doesn't have audiocodes dictionary but the user was found in the RADIUS
isEnabled	Boolean	Whether the RADIUS authentication feature is activated
port	Integer	The pot number
host	String	The host / IP address of the RADIUS server
retryCount	Integer	The number of retries in case of the failure
sharedSecret	String	The password of the RADIUS server
timeout	Integer	The connection timeout

- 200 OK
- 409 Conflict
- 500 Internal error



# 20.7.3 Test RADIUS Authentication Server

The <code><ARM\_Configurator\_IP>/ARM/v1/configuration/security/radius</code> URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to test the RADIUS Authentication Server.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/configuration/security/radius/test

### **HTTP Method**

PUT

## **Supported Content-Type**

application/json

### **Attributes**

Attribute	Туре	Description
defaultRole	ENUM	SECURITY_ADMIN,ADMIN,MONITOR,REJECT The default authentication level if the RADIUS doesn't have an AudioCodes dictionary; however, the user was found on the RADIUS server.
isEnabled	Boolean	Whether the RADIUS authentication feature is activated
port	Integer	The port number
host	String	The host / IP address of the RADIUS server
retryCount	Integer	The number of retries in case of the failure
sharedSecret	String	The password of the RADIUS server
timeout	Integer	The connection timeout
testConnectivity:{ name:String password:String }		The user name and the password to check against the RADIUS server

- 200 OK
- 409 Conflict
- 500 Internal error

# 20.8 Azure Authentication

This section describes the URLs for managing the connection with Microsoft Azure.

# 20.8.1 Get Azure Authentication Server

The <code><ARM\_Configurator\_IP>/ARM/v1/configuration/azure</code> URL when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve the Microsoft Azure authentication credentials.

### **REST Resource**

GET <ARM Configurator IP>/ARM/v1/configuration/azure

### **HTTP Method**

GET

### **Supported Content-Type**

application/json

### Attributes

Attribute	Туре	Description
isEnabled	Boolean	Whether the Azure authentication feature is activated
clientId	String	Azure AD client ID
tenantID	String	Azure AD tenant ID
clientSecret	String	Azure AD client secret
securityAdminMapping	String	Azure app role that mapped to ARM security admin level
adminMapping	String	Azure app role that mapped to ARM admin level
monitorMapping	String	Azure app role that mapped to ARM monitor level
redirectUrl	String	Microsoft redirect URL to ARM after authentication

- 200 OK
- 409 Conflict
- 500 Internal error



# 20.8.2 Update/Add Azure Authentication Server

The <ARM\_Configurator\_IP>/ARM/v1/configuration/azure URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to add or update the Microsoft Azure authentication credentials.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/configuration/azure

### **HTTP Method**

PUT

### **Supported Content-Type**

application/json

### Attributes

Attribute	Туре	Description
isEnabled	Boolean	Whether the Azure authentication feature is activated
clientId	String	
tenantID	String	
clientSecret	String	
securityAdminMapping	String	
adminMapping	String	
monitorMapping	String	

- 200 OK
- 409 Conflict
- 500 Internal error

# 20.8.3 Test Azure Authentication Server

The  $\ARM_Configurator_IP>/ARM/v1/configuration/test$  URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to test the Microsoft Azure authentication server.

### **REST Resource**

ARM Configurator IP>/ARM/v1/configuration/security/azure/test

### **HTTP Method**

PUT

# **Supported Content-Type**

application/json

### Attributes

Attribute	Туре	Description
clientId	String	
tenantID	String	
clientSecret	String	
securityAdminMapping	String	
adminMapping	String	
monitorMapping	String	

- 200 OK
- 409 Conflict
- 500 Internal error



# 20.9 Calls Configuration

# 20.9.1 Get Calls Configuration

The <code><ARM\_Configurator\_IP>/ARM/v1/configuration/calls</code> URL when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve the Calls configuration.

#### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/configuration/calls

### **HTTP Method**

GET

### **Supported Content-Type**

application/json

# Attributes

Attribute	Туре	Description
limit	Integer	The maximum number of calls that will be saved in the database.  Maximum value is 10,000,000
enabled	Boolean	Indicates whether calls will be sent by the routers and whether they will be saved in database
threshold	Integer	Indicates the time after which an open call is considered closed
includeCdrInSuccessfulCalls	Boolean	Should the entire CDR chain be saved for successful calls
includeCdrInPartialCalls	Boolean	Should the entire CDR chain be saved for partial calls

- 200 OK
- 409 Conflict
- 500 Internal error

# 20.9.2 Update Calls Configuration

The <code><ARM\_Configurator\_IP>/ARM/v1/configuration/calls</code> URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to update the Calls configuration.

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/ v1/configuration/calls

### **HTTP Method**

PUT

# **Supported Content-Type**

application/json

### Attributes

Attribute	Туре	Description
limit	Integer	The maximum number of calls that will be saved in the database.  Maximum value is 10,000,000
enabled	Boolean	Indicates whether calls will be sent by the routers and whether they will be saved in database
threshold	Integer	Indicates the time after which an open call is considered closed
includeCdrInSuccessfulCalls	Boolean	Should the entire CDR chain be saved for successful calls
includeCdrInPartialCalls	Boolean	Should the entire CDR chain be saved for partial calls

- 200 OK
- 409 Conflict
- 500 Internal error



# 20.10 Registered Users

# 20.10.1 Get Registered Users Configuration

The  $\ARM_Configurator_IP>/ARM/v1/configuration/registeredUsers$  URL when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve the registered users configuration.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/configuration/registeredUsers

### **HTTP Method**

GET

### **Supported Content-Type**

application/json

#### **Attributes**

Attribute	Туре	Description
enabled	Boolean	Enable registered users feature

# 20.10.2 Update Registered Users Configuration

The  $\ARM_Configurator_IP>/ARM/v1/configuration/registeredUsers$  URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to update the registered users configuration.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/configuration/registeredUsers

### **HTTP Method**

PUT

# **Supported Content-Type**

application/json

Attribute	Туре	Description
enabled	Boolean	Enable registered users feature

# 20.11 Analytics

# 20.11.1 Get Analytics Configuration

The <ARM\_Configurator\_IP>/ARM/v1/configuration/analytics URL when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve the Analytics configuration.

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/configuration/analytics

# **HTTP Method**

GET

### **Supported Content-Type**

application/json

Attribute	Туре	Description
password	String	Analytics user password.  This password can be any string which doesn't contain the following characters:
host1	String	IP / hostname 1 for connecting to the Analytics database using default user 'analytics'.  Default='%' you can connect using the analytics user from any IP / hostname. For
		example, " 'analytics'@'%' "; " 'analytics'@'ABC' "
host2	String	IP / hostname 2 for connecting to the Analytics database using default user 'analytics'.  Default='%'
host3	String	IP / hostname 3 for connecting to the Analytics database using default user 'analytics'  Default='%'



# 20.11.2 Update Analytics Configuration

The <ARM\_Configurator\_IP>/ARM/v1/configuration/analytics URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to update the Analytics configuration.

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/configuration/analytics

### **HTTP Method**

PUT

## **Supported Content-Type**

application/json

Attribute	Туре	Description
password	String	Analytics user password.  This password can be any string which doesn't contain the following characters:
host1	String	IP / hostname 1 for connecting to the Analytics database using default user 'analytics'.
		Default='%' you can connect using the analytics user from any IP / hostname. For example, " 'analytics'@'%' "; " 'analytics'@'ABC' "
host2	String	IP / hostname 2 for connecting to the Analytics database using default user 'analytics'.  Default='%'
host3	String	IP / hostname 3 for connecting to the Analytics database using default user 'analytics'.  Default='%'

# 20.11.3 Restore Analytics to Default

The <ARM\_Configurator\_IP>/ARM/v1/configuration/analytics/default URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to restore the Analytics configuration to default.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/configuration/analytics/default

### **HTTP Method**

PUT

### **Supported Content-Type**

application/json

# 20.11.4 Get Analytics Users

The <arm\_Configurator\_IP>/ARM/v1/configuration/analytics/users URL when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve a list of Analytics users.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/configuration/analytics/users

### **HTTP Method**

GET

### **Supported Content-Type**

application/json

Attribute	Туре	Description
[String]	[ "'analytics'@'%'",	User-defined analytics users
	"'analytics'@'ABCCorp'",  "'analytics'@'VoIP'"	



# 20.12 Registration

# 20.12.1 Get Registration

The <code><ARM\_Configurator\_IP>/ARM/v1/configuration/registration</code> URL when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve the registration configuration.

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/configuration/registration

# **HTTP Method**

GET

# **Supported Content-Type**

application/json

Attribute	Туре	Description
registrationPropertyId	Integer	The ID of the dictionary property which should be mapped to one of the following:
		<ul> <li>True: ARM Routers route Register SIP messages for the registered user.</li> </ul>
		<ul> <li>False: User is not eligible for the Register SIP message routing.</li> </ul>
dailablePropertyIds	[Integer]	List of dictionary property ids which are mapped to the dialable / address of the user. Used as the match for the user in the "To" SIP Header of the SIP Register message.
Enabled	Boolean	Indicates whether the routing of registration messages should be enabled.

# 20.12.2 Update Registration

The <code><ARM\_Configurator\_IP>/ARM/v1/configuration/registration</code> URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to update the registration configuration.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/configuration/registration

### **HTTP Method**

PUT

# **Supported Content-Type**

application/json

Attribute	Туре	Description
registrationPropertyId	Integer	The ID of the dictionary property "registration" which should be mapped to one of the following:  True: ARM Routers route Register SIP messages for the registered user.  False: User is not eligible for the Register SIP message routing.
dailablePropertyIds	[Integer]	List of dictionary property IDs which are mapped to the dialable / address of the user. Used as the match for the user in the "To" SIP Header of the SIP Register message.
Enabled	Boolean	Indicates whether the routing of registration messages should be enabled for the user. Equivalent to "Destination is a registered user in ARM" in the routing rule in the ARM Web interface.



# 20.12.3 Get Registration Users

The <code><ARM\_Configurator\_IP>/ARM/v1/configuration/registration</code> URL when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve the list of registered users.

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/configuration/registration

### **HTTP Method**

GET

# **Supported Content-Type**

application/json

Attribute	Туре	Description
[String]		Name of registered user.

# 20.13 Quota

# 20.13.1 Get Quota Configuration

The  $\ARM_Configurator_IP>/ARM/v1/configuration/quota> URL$  when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve the quota configuration.

#### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/configuration/quota

### **HTTP Method**

GET

### **Supported Content-Type**

application/json

### Attributes

Attribute	Туре	Description
warningThreshold	Integer	

- 200 OK
- 409 Conflict
- 500 Internal error



# 20.13.2 Update Quota Configuration

The  $\ARM_Configurator_IP>/ARM/v1/configuration/quota$  URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to update the quota configuration.

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/configuration/quota

### **HTTP Method**

PUT

## **Supported Content-Type**

application/json

### Attributes

Attribute	Туре	Description
warningThreshold	Integer	

- 200 OK
- 409 Conflict
- 500 Internal error

# 20.14 CAC

This section describes the URLs for managing the Call Admission Control (CAC) configuration.

# 20.14.1 Get CAC Configuration

The <ARM\_Configurator\_IP>/ARM/v1/configuration/cac URL when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve the CAC configuration.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/configuration/cac

### **HTTP Method**

GET

# **Supported Content-Type**

application/json

### **Attributes**

Attribute	Туре	Description
warningThreshold	Integer	The warning threshold value in percentages
enabled	Boolean	Is warning threshold enabled

- 200 OK
- 409 Conflict
- 500 Internal error



# 20.14.2 Update CAC Configuration

The  $\ARM_Configurator_IP>/ARM/v1/configuration/cac$  URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to update the CAC configuration.

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/configuration/cac

### **HTTP Method**

PUT

### **Supported Content-Type**

application/json

### Attributes

Attribute	Туре	Description
warningThreshold	Integer	The warning threshold value in percentages
enabled	Boolean	Is warning threshold enabled

- 200 OK
- 409 Conflict
- 500 Internal error

This page is intentionally left blank.



# 21 Calls

This section describes the URLs for calls management.

# 21.1 Get Calls Summary

The <ARM\_Configurator\_IP>/ARM/v1/configuration/calls URL when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve a summary of the Calls configuration.

#### **REST Resource**

<ARM Configurator IP>/ARM/v1/calls

#### **HTTP Method**

GET

# **Supported Content-Type**

application/json

#### **Attributes**

Attribute	Туре	Description
cursor	Integer	The next page or -1 if it is the last page
calls	{     sessionKey: String     sessionId:String     armSetupTime: Date     srcUriBeforeManipulation:String     dstUriBeforeManipulation:String     incomingNodeId:Integer     incomingPconId:Integer     outgoingNodeId:Integer     outgoingPconId:Integer     routingRuleId:Integer     sipTerminationReason:String }	Call details

- 200 OK
- 409 Conflict
- 500 Internal error

Developer's Guide 21. Calls

# 21.1.1 Filter

The Statistics API requires using a filter to control the size and content of the data. The filter should be added to the suffix of the URL as is shown in the example below:

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/calls?
filter=(incomingNodeId={id},outgoingNodeId={id})

### **HTTP Method**

GET

# **Supported Content-Type**

application/json

### Attributes

Filter	Available for these Requests	Description
incomingNodeld	calls	Equals (=)
outgoingNodeId	calls	Equals (=)
incommingPconId	calls	Equals (=)
outgoingPconId	calls	Equals (=)
startTime	calls	Equals (=)
endTime	calls	Equals (=)
dstUriBeforeManipulation	calls	Contains (~)
srcUriBeforeManipulation	calls	Contains (~)
sessionId	calls	Equals (=)
routingRuleId	calls	Equals (=)
sipTerminationReason	calls	Equals (=)

- 200 OK
- 409 Conflict
- 500 Internal error



# 21.2 Get Specific Call

The  $\ARM_Configurator_IP>/ARM/v1/calls/{sessionKey}$  URL when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve the details of a specific call.

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/calls/{sessionKey}

### **HTTP Method**

GET

# **Supported Content-Type**

application/json

Attribute	Туре	Description
sessionKey	String	Unique combination of node id and sessionId
sessionId	String	The session ID generated by the Node
armSetupTime	Date	UTC time
armReleaseTime	Date	UTC time
routerIp	String	The IP address of the initial router that calculated the path.
srcUriBeforeManipulation	String	The source URI as it was prior to manipulation.
dstUriBeforeManipulation	String	The destination URI as it was prior to manipulation.
discardingByRoutingRule	Integer	The routing rule ID of the routing rule which case the call to be discarded.
routingRuleId	Integer	The routing rule ID of the successful path, or the last path if the call failed.
partial	Boolean	Indicates whether the call was ended with all the CDR information, or if some of the data was missing.
description	String	Description regarding the call (if any).
incomingNodeId	Integer	The ID of the incoming node.

Developer's Guide 21. Calls

Attribute	Туре	Description
incommingPconId	Integer	The ID of the incoming peer connection.
incommingConnectionId	Integer	The ID of the incoming connection (only relevant to 3 <sup>rd</sup> party nodes).
outgoingNodeId	Integer	The ID of the last node in the paths chain.
outgoingPconId	Integer	The ID of the last peer connection in the paths chain.
sipTerminationReason	String	The SIP response code.
voiceDuration	Integer	Duration of the voice call in milliseconds.
preRouteManipulationsList	{     originalValue:String     manipulatedValue:String     manipulatedEntity:ENUM     manipulationsList:{     originalValue: String     manipulatedValue: String     manipulatingEntity:ENUM     manipulatingEntityName:     String     isChanged: Boolean     description: String }	<ul> <li>ManipulatingEntity         (optional)- the entity from         ARM data base/GUI         perspective which tracked         and might change the         ManipulatedEntity.</li> <li>ManipulatedEntity         (optional)- the entity that is         tracked and may change.</li> <li>originalValue: the value of         the manipulated entity         prior to manipulation (in         the case of         user/password/destIP),         these entities may be         optional as well.</li> <li>Note: When the         ManipulatingEntity is a         'RoutingRuleAction', there is         no URL.</li> </ul>



Attribute	Туре	Description
cdrSessionPathList	{     sipTerminationReason: String     sipTerminationReasonDesc:     String     routeSeq: Integer     routerlp: String     srcUriAfterManipulation: String     dstUriAfterManipulation: String     armSetupTime: Date     armReleaseTime: Date     sbcSetupTime: Date     sbcReleaseTime: Date     sbcReleaseTime: Date     sbcReleaseTime: Date     sbcAlertTime: Date     alertDuration: Integer     voiceDuration: Integer }	Represents a path of a call. If the call failed without starting this object, this field is Null.  Durations are -1 if the path fails

- 200 OK
- 409 Conflict
- 500 Internal error

Developer's Guide 22. Calls Quota

# 22 Calls Quota

This section describes the URLs for managing calls quotas.

# 22.1 Get Calls quota

The  $\ARM_Configurator_IP>/ARM/v1/calls/quota/{id}$  URL when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve the entire calls quota or the quota for a specific call.

### **REST Resource**

```
<ARM_Configurator_IP>/ARM/v1/calls/quota
<ARM Configurator IP>/ARM/v1/calls/quota/{id}
```

{id} - ID of the requested element

### **HTTP Method**

GET

# **Supported Content-Type**

application/json

### **Attributes**

Attribute	Туре	Description
id	Integer	Quota ID
name	String	Quota name
quota	Double	Quota limit
periodicity	Enum	Possible values for periodicity:  1 = MONTHLY  2 = WEEKLY  3 = DAILY
firstDayOfWeek	Enum	Possible values for day:  1 = MON 2 = TUE 3 = WED 4 = THU 5 = FRI 6 = SAT 7 = SUN  Relevant when periodicity property is equal to WEEKLY
firstDayOfMonth	Integer	Relevant when periodicity property is equal to WEEKLY
blockCalls	Boolean	block call when quota limit reached



- 200 OK
- 409 Conflict

# **22.1.1 Filter**

Quota API requires using a filter to control the size and content of the data. Filter should be added to the suffix of the URL, for example:

### **REST Resource**

<ARM Configurator IP>/ARM/v1/calls/quota?limit=20&page=1)

### HTTP Method

GET

# **Supported Content-Type**

application/json

### **Attributes**

Filter	Available for these Requests	Description
limit	qouta	Equals (=)
page	qouta	Equals (=)

- 200 OK
- 409 Conflict

Developer's Guide 22. Calls Quota

# 22.2 Add Calls Quota

The  $\ARM_Configurator_IP>/ARM/v1/calls/quota\ URL$  when used with the POST method, provides the ability for the ARM Manager to send a request to the ARM Configurator to add a calls quota.

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/calls/quota

### **HTTP Method**

POST

## **Supported Content-Type**

application/json

### **Attributes**

Attribute	Туре	Description
name	String	Quota name
quota	Double	Quota limit
periodicity	Enum	Possible values for periodicity:  1 = MONTHLY  2 = WEEKLY  3 = DAILY
firstDayOfWeek	Enum	Possible values for day:  1 = MON 2 = TUE 3 = WED 4 = THU 5 = FRI 6 = SAT 7 = SUN  Relevant when periodicity property is equal to WEEKLY
firstDayOfMonth	Integer	Relevant when periodicity property is equal to WEEKLY
blockCalls	Boolean	block call when quota limit reached



# 22.3 Update Calls Quota

The  $\ARM_Configurator_IP>/ARM/v1/calls/quota/{id}$  URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to update a specific calls quota.

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/calls/quota/{id}

### **HTTP Method**

PUT

### **Supported Content-Type**

application/json

### **Attributes**

Attribute	Туре	Description
name	String	Quota name
quota	Double	Quota limit
periodicity	Enum	Possible values for periodicity:  1 = MONTHLY  2 = WEEKLY  3 = DAILY
firstDayOfWeek	Enum	Possible values for day:  1 = MON 2 = TUE 3 = WED 4 = THU 5 = FRI 6 = SAT 7 = SUN  Relevant when periodicity property is equal to WEEKLY
firstDayOfMonth	Integer	Relevant when periodicity property is equal to WEEKLY
blockCalls	Boolean	block call when quota limit reached

Developer's Guide 22. Calls Quota

## 22.4 Delete Calls Quota

The  $\ARM_Configurator_IP>/ARM/v1/calls/quota/{id}$  URL when used with the DELETE method, provides the ability for the ARM Manager to send a request to the ARM Configurator to delete a specific calls quota.

### **REST Resource**

<ARM Configurator\_IP>/ARM/v1/calls/quota/{id}

### **HTTP Method**

DELETE

### **Supported Content-Type**

application/json

# 22.5 Delete Multiple Calls Quota

The <arm\_Configurator\_IP>/ARM/v1/ calls/quota?filter=(id=1;2;3...) URL when used with the DELETE method, provides the ability for the ARM Manager to send a request to the ARM Configurator to delete multiple calls quotas.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/ calls/quota?filter=(id=1;2;3...)

### **HTTP Method**

DELETE

### **Supported Content-Type**

application/json

#### **Attributes**

The response will be a multi response JSON with the appropriate response code for each ID that was sent

Attribute	Туре	Description
multiStatusJsonList	[	Status: the http response code for this specific ID
	status: Integer	Description: the description
	description: String id: Integer	ID: the ID of the object for this specific response
	}	
	]	



This page is intentionally left blank.

Developer's Guide 23. WEB Services

# 23 WEB Services

This chapter describes the REST API resources for Web Services. The following APIs are described:

- Get Web Services Templates
- Get Web Services Implementation
- Create Web Service Implementation
- Update Web Service Implementation
- Delete Web Service Implementation

# 23.1 Get Web Services Templates

The <ARM Configurator IP>/ARM/v1/numberPortability/template

URL when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve a Web Services template.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/numberPortability/template

The Template defines all the attributes that the operator will be able to define for a specific web service.

### **HTTP Method**

GET

### **Supported Content-Type**

application/json

### **Attributes**

Attribute	Туре	Description
id	Integer	ID of the Web services template
name	String	Name of the Web services template.
numberPortabilityAgentType	Enum	The unique ID of the template type.
params	[ name: String uiName: String value: String type:enum }	Name – the database of the parameters in the database uiName- the name of the attribute in the UI value – the default value 0 = type - stringType 1 = numberType 2 = booleanType

- 200 OK
- 409 Conflict
- 500 Internal error



# 23.2 Get Web Services Implementation

The <ARM Configurator IP>/ARM/v1/numberPortability/implementation

URL when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve a specific Web Services Implementation.

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/numberPortability/implementation
<ARM Configurator IP>/ARM/v1/numberPortability/implementation/{id}

### **HTTP Method**

GET

### **Supported Content-Type**

application/json

### **Attributes**

Implementation of one of the templates

Attribute	Туре	Description
id	Integer	ID of the Web services template
name	String	The name of the Web Service Implementation.
numberPortabilityAgentType	Enum	The unique ID of the template type.
params	[ name: String uiName: String value: String type:enum }	<ul> <li>Name – the database of the attributes in the database</li> <li>uiName- the name of the attribute in the UI</li> <li>value – the default value type:</li> <li>0 = stringType</li> <li>1 = numberType</li> <li>2 = booleanType</li> </ul>

- 200 OK
- 409 Conflict
- 500 Internal error

Developer's Guide 23. WEB Services

# 23.3 Create Web Service Implementation

The ARM\_Configurator\_IP>/ARM/v1/numberPortability/implementation URL when used with the POST method, provides the ability for the ARM Manager to send a request to the ARM Configurator to add a Web Service Implementation.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/numberPortability/implementation

### **HTTP Method**

POST

### **Supported Content-Type**

application/json

### **Attributes**

Attribute	Туре	Description
id	Integer	The ID of the Web Service Implementation
name	String	The name of the Web Service Implementation.
numberPortabilityAgentType	Enum	The unique ID of the template type.
params	[ name: String uiName: String value: String type:enum }	<ul> <li>Name – the database of the attributes in the database</li> <li>uiName- the name of the attribute in the UI</li> <li>value – the default value type:         <ul> <li>0 = stringType</li> <li>1 = numberType</li> <li>2 = booleanType</li> </ul> </li> </ul>

- 201 Created
- 409 Conflict
- 500 Internal error



# 23.4 Update Web Service Implementation

The <code><ARM\_Configurator\_IP>/ARM/v1/numberPortability/implementation/{id}</code> URL when used with the POST method, provides the ability for the ARM Manager to send a request to the ARM Configurator to update a Web Service Implementation.

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/numberPortability/implementation/{id}

### **HTTP Method**

PUT

### **Supported Content-Type**

application/json

### **Attributes**

Attribute	Туре	Description
id	Integer	The ID of the Web Service Implementation.
name	String	The name of the Web Service Implementation.
numberPortabilityAgentType	Enum	The unique ID of the template type.
params	[ name: String uiName: String value: String type:enum }	<ul> <li>Name – the database of the parameter in the databse</li> <li>uiName- the name of the attribute in the UI</li> <li>value – the default value type:         <ul> <li>0 = stringType</li> <li>1 = numberType</li> <li>2 = booleanType</li> </ul> </li> </ul>

- 200 OK
- 409 Conflict
- 500 Internal error

Developer's Guide 23. WEB Services

# 23.5 Delete Web Service Implementation

The  $\ARM_Configurator_IP>/ARM/v1/numberPortability/implementation/{id} URL when used with the DELETE method, provides the ability for the ARM Manager to send a request to the ARM Configurator to delete a Web Service Implementation.$ 

### **REST Resource**

<ARM Configurator IP>/ARM/v1/numberPortability/implementation/{id}

### **HTTP Method**

DELETE

### **Supported Content-Type**

application/json

- 200 OK
- 409 Conflict
- 500 Internal error



This page is intentionally left blank.

Developer's Guide 24. Certificates

# 24 Certificates

The URLs describes in this section can be implemented to manage the SSL connection for the ARM SSL client for authenticating the server certificate of a remote server (one-way authentication).

## 24.1 Get Certificate API

The <arm\_Configurator\_IP>/ARM/v1/certificate URL when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve a remote server certificate or root certificate from the Trusted Root Store.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/certificate

### **HTTP Method**

GET

## **Supported Content-Type**

application/json

Attribute	Туре	Description
alias	String	The name of the alias of the certificate
value	String	Base64 representation of the certificate

- 200 OK
- 409 Conflict
- 500 Internal error



# 24.2 Add Certificate API

The <ARM\_Configurator\_IP>/ARM/v1/certificate URL when used with the POST method, provides the ability for the ARM Manager to send a request to the ARM Configurator to upload a remote server certificate or root certificate to the Trusted Root Store.

### **REST Resource**

POST <ARM Configurator IP>/ARM/v1/certificate

### **HTTP Method**

POST

### **Supported Content-Type**

application/json

Attribute	Туре	Description
alias	String	The name of the alias of the certificate
value	String	Base64 representation of the certificate

- 201 Created
- 409 Conflict
- 500 Internal error

Developer's Guide 24. Certificates

# 24.3 Delete Certificate API

The <ARM\_Configurator\_IP>/ARM/v1/certificate/{alias} URL when used with the DELETE method, provides the ability for the ARM Manager to send a request to the ARM Configurator to delete a remote server certificate or root certificate from the Trusted Root Store.

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/certificate/{alias}

### HTTP Method

DELETE

## **Supported Content-Type**

application/json

- 200 OK
- 409 Conflict
- 500 Internal error



# 25 Policy Studio

This chapter describes the REST API resources for the Policy Studio. The following APIs are described:

- Get Policy Studio API
- Add Policy Studio API
- Update Policy Studio API
- Delete Policy Studio API

# 25.1 Get Policy Studio API

The  $\ARM_Configurator_IP>/ARM/v1/callSetupRule$  URL when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve a call setup rule.

### **REST Resource**

```
<ARM_Configurator_IP>/ARM/v1/callSetupRule
<ARM Configurator IP>/ARM/v1/callSetupRule/{id}
```

### **HTTP Method**

GET

## **Supported Content-Type**

application/json

Attribute	Туре	Description
id	Integer	Database ID
name	String	Name of the policy studio rule.
searchFields	{   field: enum   propertyDicEntryIds   :[ Integer ] }	Possible values for the field: SOURCE_URI_USER, SOURCE_URI_HOST, DEST_URI_USER, DEST_URI_HOST, CONTACT_URI_USER, CONTACT_URI_HOST, CONTACT_URI_PORT, P_ASSERTED_IDENTITY_DISPLAY_NAM E, P_ASSERTED_IDENTITY_USER P_ASSERTED_IDENTITY_HOST Each represents SIP header to be matched
actionFields	{   field: enum   propertyDicEntryIds   :[ Integer ]  }	Possible values for the field:  SOURCE_URI_USER, SOURCE_URI_HOST, DEST_URI_USER, DEST_URI_HOST, DEST_IP_ADDR, DEST_PORT, DEST_PROTOCOL, USER_CREDENTIALS_USER_NAME, USER_CREDENTIALS_PASSWORD, P_ASSERTED_IDENTITY_DISPLAY_NAM

Developer's Guide 25. Policy Studio

Attribute	Туре	Description
		E, P_ASSERTED_IDENTITY_USER, P_ASSERTED_IDENTITY_HOST Each represents SIP header to be changed
nodelds	[ Integer ]	Nodes to be matched
pConlds	[ Integer ]	Peer connections to be matched
topologyGroupIds	[ Integer ]	Topology Groups to be matched
priority	Integer	The priority of the policy studio rule
adminState	Enum	LOCKED, UNLOCKED
destAttr	{     attributes: {         value: String     }     attributeGroups:[     Integer ]     }	Destination attribute to match (destination number), can be either prefix, or prefix group ID
type	enum	USER, NUMBER_PORTABILITY User is the regular policy studio Number portability is the web services
numberPortabilityId	Integer	If the type is NUMBER_PORTABILITY,ID of the web service which will be done in case of a match is provided.
isRegisteredUsers	Boolean	Enables the Registered Users feature for operators to route calls to SBC registered users.
destUserGroupsIds	[ Integer ]	Destination User Group IDs
srcUserGroupsIds	[ Integer ]	Source User Group IDs
requestType	Enum	0 = CALL 1 = REGISTER
didMatchType	Enum	SRC_AND_DEST, DEST, SOURCE  This attribute is only used for DID masking web services.
poolld	Integer	<ul> <li>The ID of the "pool of numbers" prefix group,</li> <li>If defined: ARM Router chooses a free random number and manipulates the source number,</li> <li>If not defined: ARM saves the source URI and destination URI in the database without manipulating (masking) the source number.</li> <li>This attribute is only used for DID masking web services.</li> </ul>
callExpirationTime	Integer	Timeout before the call is unavailable for callback (in seconds).



Attribute	Туре	Description
		This attribute is only used for DID masking web services.
didXHeader	String	If defined, the ARM router does not manipulate the destination number for the incoming call, instead it adds it as the defined X Header; the header must start with the X-ARM- prefix.  This attribute is only used for DID masking web services.
srcNormalizationGroupId	Integer	ID of the normalization group. This normalization is performed on the source URI prior to the database lookup / persistence. This manipulation does not affect the routing.  This attribute is only used for DID masking web services.
setDestNormalizationGroupI d	Integer	ID of the normalization group. This normalization is performed on the destination URI prior to the database lookup / persistence. This manipulation does not affect the routing.  This attribute is only used for DID masking web services.
direction	Enum	Call direction:  OUTGOING INCOMING This attribute is only used for DID masking web services.
flow	Enum	STOP, CONTINUE, CONTINUE_TO_RULE
continueToRuleId	Integer	ID of the policy studio.  This attribute is only relevant when the flow attribute is set to CONTINUE_TO_RULE.

- 200 OK
- 409 Conflict
- 500 Internal error

Developer's Guide 25. Policy Studio

# 25.2 Add Policy Studio API

The  $\ARM\_Configurator\_IP>/ARM/v1/callSetupRule$  URL when used with the POST method, provides the ability for the ARM Manager to send a request to the ARM Configurator to add a Policy Studio generated call setup rule.

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/callSetupRule

### **HTTP Method**

POST

### **Supported Content-Type**

application/json

Attribute	Туре	Description
id	Integer	Database ID
name	String	Name of the policy studio rule
searchFields	{ field: enum propertyDicEntryIds :[Integer] }	Possible values for the field: SOURCE_URI_USER, SOURCE_URI_HOST, DEST_URI_USER, DEST_URI_HOST, CONTACT_URI_USER, CONTACT_URI_HOST, CONTACT_URI_PORT, P_ASSERTED_IDENTITY_DISPLAY_NAM E, P_ASSERTED_IDENTITY_USER P_ASSERTED_IDENTITY_HOST Each represents SIP header to be matched
actionFields	{ field: enum propertyDicEntryIds :[Integer] }	Possible values for the field:  SOURCE_URI_USER, SOURCE_URI_HOST, DEST_URI_USER, DEST_URI_HOST, DEST_IP_ADDR, DEST_PORT, DEST_PROTOCOL, USER_CREDENTIALS_USER_NAME, USER_CREDENTIALS_PASSWORD, P_ASSERTED_IDENTITY_DISPLAY_NAM E, P_ASSERTED_IDENTITY_USER, P_ASSERTED_IDENTITY_HOST Each represents SIP header to be changed
nodelds	[ Integer ]	Nodes to be matched
pConIds	[ Integer ]	Peer connections to be matched
priority	Integer	The priority of the policy studio rule
prevId	Integer	The ID of the previous policy studio rule, -1 if first
nextld	Integer	The ID of the next policy studio rule, -1 if last
adminState	Enum	LOCKED, UNLOCKED



Attribute	Туре	Description
destAttr	{   attributes: {     value: String } attributeGroups:[ Integer] }	Destination attribute to match (destination number), can be either prefix, or prefix group ID
type	enum	USER, NUMBER_PORTABILITY User is the regular policy studio Number portability is the web services
numberPortabilityId	Integer	If the type is NUMBER_PORTABILITY, ID of the Web service which will be done in case of a match must be provided
isRegisteredUsers	Boolean	Enables the Registered Users feature for operators to route calls to SBC registered users ("Destination is a registered user in ARM" check box in ARM GUI).
destUserGroupsIds	[ Integer ]	The list of Destination User Group IDs
srcUserGroupsIds	[ Integer ]	The list of Source Group IDs
requestType	Enum	0 = CALL 1 = REGISTER
didMatchType	Enum	SRC_AND_DEST, DEST, SOURCE This attribute is only used for DID masking web services.
poolld	Integer	This attribute is only used for DID masking web services.
callExpirationTime	Integer	This attribute is only used for DID masking web services.
didXHeader	Integer	This attribute is only used for DID masking web services.
srcNormalizationGroupId	Integer	This attribute is only used for DID masking web services.
setDestNormalizationGroup Id	Integer	This attribute is only used for DID masking web services.
direction	Enum	This attribute is only used for DID masking web services. OUTGOING, INCOMING
flow	Enum	This attribute is only used for DID masking web services. STOP, CONTINUE, CONTINUE_TO_RULE
continueToRuleId	Integer	This attribute is only used for DID masking web services.

- 201 Created
- 409 Conflict
- 500 Internal error

Developer's Guide 25. Policy Studio

# 25.3 Update Policy Studio API

The <ARM\_Configurator\_IP>/ARM/v1/callSetupRule URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to update a Policy Studio generated call setup rule.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/callSetupRule/{id}

### **HTTP Method**

PUT

### **Supported Content-Type**

application/json

### **Attributes**

Attribute	Туре	Description
id	Integer	Database ID
name	String	Name of Policy Studio rule.
searchFields	{ field: enum propertyDicEntryIds :[Integer] }	Possible values for the field: SOURCE_URI_USER, SOURCE_URI_HOST, DEST_URI_USER, DEST_URI_HOST, CONTACT_URI_USER, CONTACT_URI_HOST, CONTACT_URI_PORT, P_ASSERTED_IDENTITY_DISPLAY_NAM E, P_ASSERTED_IDENTITY_USER P_ASSERTED_IDENTITY_HOST Each represents SIP header to be matched
actionFields	{ field: enum propertyDicEntryIds :[Integer] }	Possible values for the field: SOURCE_URI_USER, SOURCE_URI_HOST, DEST_URI_USER, DEST_URI_HOST, DEST_IP_ADDR, DEST_PORT, DEST_PROTOCOL, USER_CREDENTIALS_USER_NAME, USER_CREDENTIALS_PASSWORD, P_ASSERTED_IDENTITY_DISPLAY_NAM E, P_ASSERTED_IDENTITY_USER, P_ASSERTED_IDENTITY_HOST Each represents SIP header to be changed
nodelds	[ Integer ]	Nodes to be matched
pConlds	[Integer]	Peer connections to be matched
priority	Integer	The priority of the policy studio rule
prevld	Integer	The ID of the previous policy studio rule, -1 if first
nextld	Integer	The ID of the next policy studio rule, -1 if last
adminState	Enum	LOCKED, UNLOCKED



Attribute	Туре	Description
destAttr	{   attributes: {    value: String }   attributeGroups:[ Integer] }	Destination attribute to match (destination number), can be either prefix, or prefix group ID
type	enum	USER, NUMBER_PORTABILITY User is the regular policy studio Number portability is the web services
numberPortabilityId	Integer	If the type is NUMBER_PORTABILITY, ID of the web service which will be done in case of a match must be provided
isRegisteredUsers	Boolean	Indicates whether the user is registered.
destUserGroupsIds	[ Integer ]	The list of Destination User Group IDs
srcUserGroupsIds	[ Integer ]	The list of Source User Group IDs
requestType	Enum	0 = CALL 1 = REGISTER
didMatchType	Enum	SRC_AND_DEST, DEST, SOURCE This attribute is only used for DID masking web services.
poolld	Integer	Only for DID masking web services
callExpirationTime	Integer	Only for DID masking web services
didXHeader	Integer	This attribute is only used for DID masking web services.
srcNormalizationGroupId	Integer	This attribute is only used for DID masking web services.
setDestNormalizationGroup Id	Integer	This attribute is only used for DID masking web services.
direction	Enum	This attribute is only for DID masking web services. OUTGOING, INCOMING
flow	Enum	This attribute is only used for DID masking web services.  STOP, CONTINUE, CONTINUE_TO_RULE
continueToRuleId	Integer	This attribute is only used for DID masking web services.

- 200 OK
- 409 Conflict
- 500 Internal error

Developer's Guide 25. Policy Studio

# 25.4 Delete Policy Studio API

The  $\ARM_Configurator_IP>/ARM/v1/callSetupRule$  URL when used with the DELETE method, provides the ability for the ARM Manager to send a request to the ARM Configurator to delete a Policy Studio generated call setup rule.

### **REST Resource**

DELETE <ARM Configurator IP>/ARM/v1/callSetupRule/{id}

- 200 OK
- 409 Conflict
- 500 Internal error



# 26 CAC Profile

This chapter describes the REST API resources for the CAC Profile. The following APIs are described:

- Get CAC Profile
- Add CAC Profile
- Update CAC Profile
- Delete CAC Profile

# 26.1 Get CAC Profile

The <ARM\_Configurator\_IP>/ARM/v1/cac/profile/{id} URL when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve all CAC profiles or a specific CAC profile.

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/cac/profile
<ARM Configurator IP>/ARM/v1/cac/profile/{id}

{id} - ID of the requested element

### **HTTP Method**

GET

### **Supported Content-Type**

application/json

Attribute	Туре	Description
id	Integer	CAC Profile ID
name	String	CAC Profile name
totalLimit	Long	Maximum number of allowed simultaneous sessions in the network
incomingLimit	Long	Maximum number of allowed incoming simultaneous sessions in the network
outgoingLimit	Long	Maximum number of allowed outgoing simultaneous sessions in the network

- 200 OK
- 409 Conflict

Developer's Guide 26. CAC Profile

# **26.1.1 Filter**

Cac API requires using a filter to control the size and content of the data. Filter should be added to the suffix of the URL, for example:

## **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/cac/profile?limit=20&page=2)

### **HTTP Method**

GET

## **Supported Content-Type**

application/json

### Attributes

Filter	Available for these Requests	Description
limit	Integer	Equals (=)
page	Integer	Equals (=)

- 200 OK
- 409 Conflict



# 26.2 Add CAC Profile

The  $\ARM_Configurator_IP>/ARM/v1/cac/profile$  URL when used with the POST method, provides the ability for the ARM Manager to send a request to the ARM Configurator to add a CAC profile.

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/cac/profile

### **HTTP Method**

POST

### **Supported Content-Type**

application/json

Attribute	Туре	Description
name	String	CAC Profile name
totalLimit	Long	If totalLimit is set incomingLimit and outgoingLimit should be empty
incomingLimit	Long	If incomingLimit or outgoingLimit is set totalLimit should be empty
outgoingLimit	Long	If incomingLimit or outgoingLimit is set totalLimit should be empty

- 201 Created
- 409 Conflict
- 500 Internal error

Developer's Guide 26. CAC Profile

# 26.3 Update CAC Profile

The  $\ARM_Configurator_IP>/ARM/v1/cac/profile/{id}$  URL when used with the PUT method, provides the ability for the ARM Manager to send a request to the ARM Configurator to update a CAC profile.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/cac/profile/{id}

### **HTTP Method**

PUT

### **Supported Content-Type**

application/json

### **Attributes**

Attribute	Туре	Description
name	String	CAC Profile name
totalLimit	Long	If totalLimit is set incomingLimit and outgoingLimit should be empty
incomingLimit	Long	If incomingLimit or outgoingLimit is set totalLimit should be empty
outgoingLimit	Long	If incomingLimit or outgoingLimit is set totalLimit should be empty

- 200 OK
- 409 Conflict
- 500 Internal error



# 26.4 Delete CAC Profile

The  $\ARM_Configurator_IP>/ARM/v1/calls/quota/{id}$  URL when used with the DELETE method, provides the ability for the ARM Manager to send a request to the ARM Configurator to delete a specific CAC profile.

### **REST Resource**

DELETE <ARM\_Configurator\_IP>/ARM/v1/ cac/profile/{id}

### **HTTP Method**

DELETE

- 200 OK
- 409 Conflict
- 500 Internal error

Developer's Guide 27. Journal

# 27 Journal

This chapter describes the URLs for managing journal entries.

# 27.1 Get Journal

The  $\ARM_Configurator_IP>/ARM/v1/journal$  URL when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve pages of journal entries.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/journal

### **HTTP Method**

GET

## **Supported Content-Type**

application/json

### **Attributes**

Attribute	Туре	Description
totalPages	Integer	Total pages according to the limit selected
totalElements	Integer	Total number of journal entries
numberOfElementsInPage	Integer	Total of journal entries in the current page
pageNumber	Integer	Current page
elements	{     Id: Integer     source: String     createDate: Date     description: String     value: String     action: enum     actionDescription: String }	value – the JSON object that was used to do the action, or null if didn't have a body  action – enum of the action  actionDescription – textual description of the action



## **27.1.1** Filter

The Statistics API requires using a filter to control the size and content of the data. Filter should be added to the suffix of the URL, for example:

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/journal?
filter=(searchString={string},description={String})&limit=25

### **HTTP Method**

GET

## **Supported Content-Type**

application/json

### **Attributes**

Filter	Available for these requests	Description
searchString	calls	Contains (~)
value	calls	Equals (=)
description	calls	Contains (~)
operator	calls	Equals (=) or Contains (~)
source	calls	Equals (=)
action	calls	Contains (~)
startDate	calls	Equals (=)
endDate	calls	Equals (=)
limit	calls	Equals (=)
page	calls	Equals (=)
sort	calls	DESC or ASC

- 200 OK
- 409 Conflict
- 500 Internal error

Developer's Guide 27. Journal

# 27.1.2 Get Specific Journal Entry

The <code><ARM\_Configurator\_IP>/ARM/v1/journal</code> URL when used with the GET method, provides the ability for the ARM Manager to send a request to the ARM Configurator to retrieve specific journal entries.

### **REST Resource**

<ARM\_Configurator\_IP>/ARM/v1/journal/{id}

### **HTTP Method**

GET

## **Supported Content-Type**

application/json

### Attributes

Attribute	Туре	Description
Id	Integer	Database ID
source	String	The source of the journal, generally ARM
createDate	Date	The creation date of the journal entry in UTC
description	String	Description of the action
Value	String	The JSON value if any of the body request
Action	ENUM	An action enumerator
actionDescription	String	Textual description of the action enumerator

- 200 OK
- 409 Conflict
- 500 Internal error



This page is intentionally left blank.

Developer's Guide 28. Logging

# 28 Logging

This chapter describes the REST resources for logging.

# 28.1 Client Logging into the Server

The  $\ARM_Configurator_IP>/ARM/v1/logging/client$  when used with the POST method, provides the ability for the ARM Manager to send a request to the ARM Configurator to send an error log message to a dedicated log file on the server.

### **REST Resource**

<ARM Configurator IP>/ARM/v1/logging/client

### **HTTP Method**

POST

### **Supported Content-Type**

application/json

### **Attributes**

The request MUST contain JSON data that consists of the following elements:

Attribute	Туре	Description
message	String	The message to be logged to the log file

- 201 Created The log message was created successfully to the log file.
- 409 Conflict
- 500 Internal error



This page is intentionally left blank.

# 29 REST Responses Codes

The following is a summary of the status codes for responses that will be used in the API:

- 200 OK Indicates that a successful request has been completed.
- 201 Created Indicates the successful creation of a new resource and corresponding JSON is sent.
- 202 Accepted Indicates that the request has been accepted for processing, however the processing has not yet been completed.
- 204 No Content Response a successful request has been completed without a response body (the result was empty).
- 401 Unauthorized Indicates that that the username or password of an existing WEB user is not correct.
- **403 Forbidden** Indicates that the existing WEB user does not have privileges to execute this request (incorrect credentials are sent or if the role of the user didn't match the security administrator's credentials).
- 409 Conflict Indicates that there is a conflict in the request.
- 500 Internal Error the server encountered an internal error

### **International Headquarters**

1 Hayarden Street, Airport City Lod 7019900, Israel

Tel: +972-3-976-4000 Fax: +972-3-976-4040

### AudioCodes Inc.

200 Cottontail Lane Suite A101E Somerset NJ 08873

Tel: +1-732-469-0880 Fax: +1-732-469-2298

Contact us: https://www.audiocodes.com/corporate/offices-worldwide

Website: https://www.audiocodes.com/

©2021 AudioCodes Ltd. All rights reserved. AudioCodes, AC, HD VoIP, HD VoIP Sounds Better, IPmedia, Mediant, MediaPack, What's Inside Matters, OSN, SmartTAP, User Management Pack, VMAS, VoIPerfect, VoIPerfectHD, Your Gateway To VoIP, 3GX, VocaNom, AudioCodes One Voice, AudioCodes Meeting Insights, AudioCodes Room Experience and CloudBond are trademarks or registered trademarks of AudioCodes Limited. All other products or trademarks are property of their respective owners. Product specifications are subject to change without notice.

Document #: LTRT-41965

